





# Applied Chemistry

Theory and Practice



O P Vermani  
A K Narula

# Applied Chemistry

## Theory and Practice

**O.P. VERMANI**  
Asstt. Prof. in Chemistry  
Regional Engineering College  
Kurukshetra

**A.K. NARULA**  
Lecturer in Chemistry  
Kurukshetra University  
Kurukshetra



UBS Publishers' Distributors Ltd  
8/1-B, Chowringhee Lane, Calcutta-700 016  
Ph:212451, 249473



# WILEY EASTERN LIMITED

New Delhi   Bangalore   Bombay   Calcutta   Madras   Hyderabad   Pune



I.C.H.R.T. W.B. LIBRARY

Date

10.8.98

10.8.98

Acqn. No.

9690

9690

Copyright © 1989, Wiley Eastern Limited

WILEY EASTERN LIMITED

4835/24, Ansari Road, Daryaganj, New Delhi 110 002

6, Shri B.P. Wadia Road, Basavangudi, Bangalore 560 004

Post Box No. 4124, Saraswati Mandir School, Kennedy Bridge,

Nana Chowk, Bombay 400 007

40/8, Ballygunge Circular Road, Calcutta 700 019

Post Box No. 8604, Thiruvanniyur, Madras 600 041

Post Box No. 1150, Himayath Nagar, P.O., Hyderabad 500 029

Flat No. 2, Building No. 7, Indira Co-op. Housing Society Ltd.,

Indira Heights, Pand Fatta, Erandawane, Karwe Road, Pune 411 038.

This book or any part thereof may not be  
reproduced in any form without the  
written permission of the publisher

This book is not to be sold outside the  
country to which it is consigned by  
Wiley Eastern Limited

ISBN 81-224-0170-8

Published by Mohinder Singh Sejwal for Wiley Eastern Limited,  
4835/24, Ansari Road, Daryaganj, New Delhi-110 002 and printed by  
Pradeep Singh at Siba Exim Pvt. Ltd., B-11/23, Krishna Nagar, Delhi-110 051.  
Printed in India



## Preface

As not many books are available on Experiments in Applied Chemistry, the students of technical institutions have mainly to depend on class notes or spend much time and labour in collecting material from various sources. This book is an attempt to fill that void. We have endeavoured to cover a large number of experiments which are of interest to students of chemistry in technical institutions. The book will also be of assistance to teachers in planning laboratory work.

The book has been divided into eight chapters. The first chapter describes the preparation of solutions of reagents needed in the various tests included in the manual. The second chapter comprises a number of elementary experiments which are intended to give the students a practical knowledge of the concepts of chemical equilibrium and speeds of reactions and the factors that govern them. The chapters on Water, Lubricating oils, Greases & Emulsions and Coal describe the methods of a large number of tests that are routinely carried out on these materials. The sixth chapter deals with the analysis of certain ores and alloys followed by a chapter that describes the analysis of a small number of industrially important materials. The last chapter provides solutions of exercises given at the end of various experiments. It is hoped that this chapter will equip the students well for the viva-voce examination.

This book is the outcome of many years of experience in conducting laboratory classes in applied chemistry. A large number of books have also been consulted and are listed under Bibliography. The salient features of the book are:

- (i) The theoretical principles on which the various tests are based have been elaboratively explained.
- (ii) The significance and utility of the various tests have been discussed in detail.
- (iii) For each method important precautions and their 'why' have been given.
- (iv) To help the students probe their grasp of the subject matter, a number of exercises have been included after every method.

This book could not have been possible without the able guidance and valuable suggestions of Dr. R.L. Kaushik, Professor and Chairman, Department of Chemistry, Regional Engineering College, Kurukshetra and Prof. R.N. Kapoor, Professor, Department of Chemistry, Delhi University, Delhi. We also acknowledge all the help and encouragement received from our friends and colleagues.



Despite our best efforts, errors may have crept in. We will be thankful to our readers for bringing them to our notice. Suggestions for improvement will also be received with gratitude.

**Authors**

# Contents

## Preface

iii

### 1. Preparation of Solutions of the Reagents

- 1.1 Alkali Solutions 1
- 1.2 Buffer Solutions 1
- 1.3 Diluted Acids 1
- 1.4 Indicator Solutions 2
- 1.5 Standard Solutions 3
- 1.6 Solutions of Approximate Strength 6
- 1.7 Titration Solvents for Acid Value of Oils 8
- 1.8 Wij's Solution 8

### 2. Chemical Equilibrium and Chemical Kinetics

10

#### 2.1 Chemical Equilibrium 10

- 2.1.1 To study the effect of addition of solutions of  $\text{Fe}(\text{NO}_3)_3$ ,  $\text{KSCN}$ ,  $\text{SnCl}_2$  or  $\text{KNO}_3$  to the equilibrium system obtained by mixing aqueous solutions of  $\text{Fe}(\text{NO}_3)_3$  and  $\text{KSCN}$  11
- 2.1.2 To study the effect of addition of  $\text{H}_2\text{O}$  and  $\text{HCl}$  on the equilibrium represented by



and to show that the observations are in accord with Le Chatelier's Principle 13

#### 2.2 Rate of a Reaction 15

- 2.2.1 Factors affecting the rate of a reaction 15
- 2.2.2 To study the effect of Concentration and Temperature on the rate of reaction between iodic acid and sodium bisulphite 17
- 2.2.3 To study the effect of nature of reactants on the rate of reaction 18
- 2.2.4 To study the catalysing effect of  $\text{Mn}^{2+}$  ions on the rate of reaction between oxalate and permanganate ions in acid medium 19
- 2.2.5 To study the effect of Surface Area on the rate of a reaction 20

#### 2.3 Velocity Constant and Order of a Reaction 22

- 2.3.1 Kinetics of a First Order Reaction 22
- 2.3.2 To determine the Rate Constant of hydrolysis of methyl acetate by dilute  $\text{HCl}$  and to show that it is a First Order reaction 23
- 2.3.3 To compare the Strengths of  $\text{HCl}$  and  $\text{H}_2\text{SO}_4$  by studying their catalysing action on hydrolysis of methyl acetate 26
- 2.3.4 To determine the Temperature Coefficient of hydrolysis of methyl acetate by acid and to calculate the Energy of Activation of the reaction 27
- 2.3.5 Kinetics of a Second Order Reaction 29
- 2.3.6 To determine the Rate Constant of hydrolysis of ethyl acetate by



NaOH (saponification) and to show that it is a Second Order reaction 29

### 3. Water

34

- 3.1 Acidity and Alkalinity of water 35
  - 3.1.1 Determination of Free  $\text{CO}_2$  in a sample of water 36
  - 3.1.2 Determination of Acidity of a water sample 38
  - 3.1.3 Determination of Alkalinity of a water sample 39
- 3.2 Chloride Content 43
  - 3.2.1 Determination of Chloride Content of a water sample by Mohr's Method (Argentometric) 44
- 3.3 Hardness 46
  - 3.3.1 Outline of Various Methods 48
  - 3.3.2 Determination of Hardness by EDTA 49
- 3.4 Dissolved Oxygen (D.O.) and Oxygen Demand 56
  - 3.4.1 Determination of Oxygen dissolved in a water sample 56
  - 3.4.2 Biochemical Oxygen Demand (BOD) 60
  - 3.4.3 Determination of Chemical Oxygen Demand (C.O.D.) of a waste water sample 62
- 3.5 Residual Chlorine and Chlorine Demand 65
  - 3.5.1 Determination of Total Chlorine Residuals (Iodometric Method) 66
  - 3.5.2 Determination of Free Chlorine Residuals and Combined Chlorine Residuals (Chloramine and Dichloramine) in a Treated water (DPD—Ferrous Titrimetric Method) 67
  - 3.5.3 Chlorine Demand 69
  - 3.5.4 Determination of the amount of Bleaching Powder required to disinfect a water sample by Horrock's Test 69
- 3.6 Turbidity and Coagulation 72
  - 3.6.1 Determination of Turbidity between 25-1000 JTU by Jackson Turbidimeter 73
  - 3.6.2 Determination of Turbidity between 5-100 JTU with Bottle Standards 73
  - 3.6.3 Coagulation 74
  - 3.6.4 To determine the minimum dose of a Coagulant required to coagulate a given sample by Jar Test and to compare the effectiveness of aluminium sulphate and ferric sulphate as coagulants for a given sample at room temperature 75
- 3.7 Solids 77
  - 3.7.1 Classification 77
  - 3.7.2 Determination of 'Total Solids' 78
  - 3.7.3 Determination of 'Total Suspended Solids' dried at  $103-105^\circ\text{C}$  Procedure 79
  - 3.7.4 Determination of 'Total Dissolved Solids' dried at  $180^\circ\text{C}$  80
  - 3.7.5 Determination of 'Fixed' and 'Volatile' Solids 81
  - 3.7.6 Determination of 'Settleable Solids' by Imhoff Cone 81

### 4. Lubricating Oils, Greases and Emulsions

83

- 4.1 Oils 84
- 4.2 Viscosity and Viscosity Index 85
  - 4.2.1 Determination of Viscosity of the given oil with Redwood Viscometer Theory 87
- 4.3 Cloud and Pour Points 91
  - 4.3.1 Determination of Cloud Point of an Oil 92



4.3.2	Determination of Pour Point of an Oil	92
4.4	Flash and Fire Points	94
4.4.1	Determination of Flash Point by Abel's Flash Point Apparatus	95
4.5	Aniline Point	97
4.5.1	Determination of Aniline Point of an Oil	98
4.6	Neutralisation Number	100
4.6.1	Determination of Total Acid Value of an Oil	101
4.6.2	Determination of Strong Acid Number or Inorganic Acidity of an Oil	102
4.7	Saponification Value or Number or Koettsoerfer Number	103
4.7.1	Determination of Saponification Value of an Oil	104
4.8	Iodine Value	105
4.8.1	Determination of Iodine Value of an Oil	107
4.9	Emulsions	108
4.9.1	Water Emulsion Test	110
4.9.2	Steam Emulsion Number	110
4.10	Greases	112
4.10.1	Consistency or Mechanical Stability	112
4.10.2	Determination of Penetration Number of a Grease	113
4.10.3	Dropping Point	115
4.10.4	Determination of Dropping Point of a Grease	115
5.	<b>Coal</b>	118
5.1	Proximate Analysis	118
5.2	Moisture Content	119
5.2.1	Determination of Inherent Moisture of a Coal/Coke sample	119
5.3	Ash Content	120
5.3.1	Determination of Ash Content of a Coal/Coke sample	121
5.4	Volatile Matter	122
5.4.1	Determination of Volatile Matter of a Coal sample	123
5.5	Fixed Carbon	124
5.6	Ultimate Analysis	125
5.7	Carbon and Hydrogen	125
5.8	Sulphur in Coal	126
5.8.1	Determination of Sulphur Content of a sample of Coal	127
5.9	Nitrogen in Coal	129
5.9.1	Determination of Nitrogen in a Coal sample	130
5.10	Oxygen Content of Coal	132
5.11	Combustion of a Carbonaceous Fuel—Flue Gas	133
5.11.1	Determination of the percentage of $\text{CO}_2$ , $\text{CO}$ , $\text{O}_2$ and $\text{N}_2$ in a Flue Gas by Orsat's Apparatus	134
6.	<b>Ores and Alloys</b>	138
6.1	Iron Ore	138
6.1.1	Determination of the amount of $\text{Fe}^{2+}$ and Total Iron in the iron ore solution by $\text{K}_2\text{Cr}_2\text{O}_7$	139
6.1.2	Determination of the amount of Iron in the iron ore solution by $\text{KMnO}_4$	143
6.2	Copper Ore and Brass	145



6.2.1	Determination of the amount of Copper in a solution of copper ore or brass	146
6.3	Silver Ore and Silver Alloy	150
6.3.1	Determination of the amount of Silver in a solution of silver ore or alloy	150
6.4	Pyrolusite	152
6.4.1	Determination of Available Oxygen in Pyrolusite iodometrically	153
6.4.2	Determination of Available Oxygen in Pyrolusite by $\text{KMnO}_4$	156
6.4.3	Determination of Available Oxygen in Pyrolusite by $\text{KIO}_3$	158
6.5	Calcium Carbonate Minerals	160
6.5.1	Determination of the amount of Calcium in Limestone	162
7.	<b>Miscellaneous</b>	<b>166</b>
7.1	Lime	166
7.1.1	Determination of Available Lime or Free $\text{CaO}$ in Industrial Lime or in Milk of Lime or Determination of Caustic Value of Agricultural Lime iodimetrically	166
7.1.2	Determination of Available Lime with standard acid	168
7.2	Plant Nutrients	169
7.2.1	Nitrogen	170
7.2.2	Determination of Total Nitrogen Content of soil, manure or a fertilizer	170
7.2.3	Phosphorus	173
7.2.4	Determination of Phosphate Content of the given soil extract, fertilizer solution or phosphate rock solution	173
7.3	Bleaching Powder	176
7.3.1	Determination of the percentage of 'Available Chlorine' in a given sample of Bleaching Powder by Bunsen's Method	177
7.4	Surface Tension	179
7.4.1	Determination of Surface Tension of a liquid, say $\text{CCl}_4$ , benzene, alcohol, etc. by Drop Number Method	181
8.	<b>Answers of Exercises</b>	<b>185</b>
	<i>Bibliography</i>	237
	<i>Index</i>	239

## Preparation of Solutions of the Reagents

### 1.1 Alkali Solutions

*Ammonia solution (1:1)* : Mix equal volumes of concentrated ammonia solution (Sp. gr. 0.88) and boiled-out distilled water.

*Ammonium hydroxide (5 N)* : Dilute 333 ml of concentrated ammonia solution (15 N, 28.4%) to 1 litre with boiled-out distilled water.

*Potassium hydroxide (5 N)* : Dissolve 280 g of A.R. KOH (Mol. wt. 56) pellets in 1 litre of boiled-out distilled water.

*Sodium hydroxide (5 N)* : Dissolve 200 g of A.R. NaOH (Mol. wt. 40) pellets in 1 litre of boiled-out distilled water.

### 1.2 Buffer Solutions

*Ammonium chloride-ammonium hydroxide buffer (pH ~ 10)* : Dissolve 68 g of A.R.  $\text{NH}_4\text{Cl}$  in some boiled-out distilled water. Add 572 ml of concentrated ammonia solution and dilute to 1 litre.

*Calcium precipitating buffer (pH ~ 8)* : Dissolve 6.0 g of A.R.  $(\text{NH}_4)_2\text{C}_2\text{O}_4$  (ammonium oxalate) in about 100 ml of boiled-out distilled water. Add 144 g of A.R.  $\text{NH}_4\text{Cl}$ , 13 ml of concentrated ammonia solution and dilute to 1 litre.

*Phosphate buffer (pH 6.2-6.5)* : Dissolve 24 g of anhydrous disodium hydrogen phosphate ( $\text{Na}_2\text{HPO}_4$ ), 46 g of anhydrous potassium dihydrogen phosphate ( $\text{KH}_2\text{PO}_4$ ) and 0.8 g of EDTA (disodium salt) in 1 litre of distilled water.

### 1.3 Diluted Acids

*Acetic acid (5 N)* : Dilute 287 ml of A.R. glacial acetic acid (17.4 N, 99.5%) to 1 litre.

*Hydrochloric acid (5 N)* : Dilute 430 ml of concentrated A.R. hydrochloric acid (11.6 N, 36%) to 1 litre.



## 2 APPLIED CHEMISTRY

**Nitric acid (5 N) :** Dilute 309 ml of concentrated A.R. nitric acid (16.2 N, 72%) to 1 litre.

**Sulphuric acid (5 N) :** Add slowly 139 ml of concentrated A.R. sulphuric acid (36 N, 96%) to distilled water, cool and dilute to 1 litre.

### 1.4 Indicator Solutions

**Calcon :** Dissolve 0.2 g of the dyestuff [sodium-1-(2-hydroxy-1-naphthylazo)-2-naphthol-4-sulphonate] in 50 ml of methanol.

**DPD (N, N-Diethyl-p-phenylenediamine) :** Dissolve 0.15 g of DPD oxalate or 0.15 g of DPD sulphate pentahydrate or 0.11 g of anhydrous DPD sulphate in boiled-out distilled water containing 1 ml of dilute sulphuric acid (1 part  $\text{H}_2\text{SO}_4$  + 3 parts water) and 20 mg EDTA. Dilute to 100 ml.

**Erichrome Black T :** Dissolve 0.2 g of the solid dyestuff in 15 ml of triethanolamine and 5 ml ethanol or dissolve 0.5 g of the dyestuff in 100 ml rectified spirit.

**Ferric alum :** Dissolve 25 g of  $\text{Fe}_2(\text{SO}_4)_3 \cdot (\text{NH}_4)_2\text{SO}_4 \cdot 24\text{H}_2\text{O}$  in about 100 ml of hot distilled water. Add 10 ml of A.R.  $\text{HNO}_3$ , boil (until the reddish-brown colour changes to yellow) to expel nitrous acid. Cool and filter.

**Ferrouin :** Dissolve 1.485 g of o-phenanthroline monohydrate and 0.695 g  $\text{FeSO}_4 \cdot 7\text{H}_2\text{O}$  in boiled-out distilled water and dilute to 100 ml. (The indicator solution itself may be purchased from the market).

**Methyl orange :** Dissolve 50 mg of methyl orange (free acid) in distilled water and dilute to 100 ml. Filter, if a precipitate is formed.

**Methyl red :** Dissolve 0.1 g of methyl red (free acid) in 100 ml of hot distilled water and cool. Filter, if necessary.

OR

Dissolve 0.1 g in 60 ml of distilled alcohol and add 40 ml of distilled water.

**p-Naphtholbenzoin :** Dissolve 1 g of the indicator powder in 100 ml of isopropyl alcohol.

**Phenolphthalein :** Dissolve 0.5 g of phenolphthalein in 50 ml of ethyl alcohol and add 50 ml of boiled-out distilled water with constant stirring. Filter, if necessary.

**Potassium chromate :** Dissolve 5.0 g of A.R. potassium chromate in 100 ml of distilled water.



*Sodium diphenylamine sulphonate* : Dissolve 0.2 g of the substance in 100 ml of boiled-out distilled water.

*Starch* : Add a little distilled water to about 0.5 g of soluble starch (A.R.) taken in a beaker. Stir with a glass rod and heat to make a transparent paste. Pour into it about 100 ml of boiling distilled water with constant stirring and cool.

### 1.5 Standard Solutions

*Alcoholic potassium hydroxide (N/100)* : Dissolve about 6 g of A.R. KOH (Mol. wt. 56, Eq. wt. 56) pellets in 1 litre of isopropyl alcohol or ethyl alcohol (distilled from potassium hydroxide) by boiling. Allow to stand, filter through sintered glass crucible and standardise with N/10 oxalic acid solution.

Prepare N/100 solution by appropriate dilution with isopropyl alcohol or ethyl alcohol (the same solvent as used in the preparation of the solution).

*Copper sulphate (N/10)* : Dissolve 24.96 g of A.R.  $\text{CuSO}_4 \cdot 5\text{H}_2\text{O}$  (Mol. wt. 249.6, Eq. wt. 249.6) in boiled-out distilled water and dilute to 1 litre.

*EDTA (N/50, 1 ml EDTA  $\equiv$  1 mg  $\text{CaCO}_3$ )* : Dissolve 3.7225 g of A.R. disodium ethylenediamine tetra-acetate dihydrate ( $\text{Na}_2\text{H}_2\text{C}_{10}\text{H}_{12}\text{O}_8\text{N}_2 \cdot 2\text{H}_2\text{O}$ , Mol. wt. 372.25, Eq. wt. 186.125), dried at  $80^\circ\text{C}$ , in boiled-out distilled water and dilute to 1 litre.

*Ethyl acetate (M/25)* : Dilute 4.0 ml of pure ethyl acetate (Mol. wt. 88.1, sp. gr. 0.9005 g/ml at  $20^\circ\text{C}$ ) to 100 ml with boiled-out distilled water. Measure 97.85 ml of the above solution and dilute to 1 litre with boiled-out distilled water.

*Ferrous ammonium sulphate (N/4)* : Dissolve 49 g of A.R.  $\text{Fe}(\text{NH}_4)_2(\text{SO}_4)_2 \cdot 6\text{H}_2\text{O}$  in boiled-out distilled water containing 10 ml of concentrated sulphuric acid and dilute to 500 ml. Standardise with N/4 potassium dichromate solution.

*Ferrous ammonium sulphate (N/100)* : Prepare by appropriate dilution of the above solution.

*Hard water (1 ml  $\equiv$  1 mg  $\text{CaCO}_3$ )* : Add slowly a small amount of dilute hydrochloric acid, through a funnel, to 1 g of anhydrous  $\text{CaCO}_3$  (A.R. grade) taken in a conical flask. Boil gently to remove  $\text{CO}_2$ . Heat to dryness on a water bath. Dissolve in boiled-out distilled water and dilute to 1 litre.

*Hydrochloric acid (N/2)* : Dilute 45 ml of concentrated A.R. hydrochloric acid to 1 litre with distilled water and standardise with N/2 sodium



#### 4 APPLIED CHEMISTRY

carbonate solution using methyl orange indicator. Make exactly N/2 by appropriate dilution.

*Hydrochloric acid (N/10)* : Dilute 9 ml of concentrated A.R. hydrochloric acid to 1 litre with distilled water and standardise with N/10  $\text{Na}_2\text{CO}_3$ . Make exactly N/10 by appropriate dilution.

*Iodine solution (N/10)* : Place about 10 g of A.R. KI (iodate-free) and 2-3 ml distilled water in a large weighing bottle fitted with a ground-glass stopper. Dissolve by gentle shaking and weigh accurately, after the bottle and the solution have reached room temperature. Introduce quickly 3.2-3.5 g of A.R. or resublimed iodine (weighed on a rough balance) into the weighing bottle, without splashing, and restopper it. Shake and let stand for sometime. After the temperature has reached equilibrium, reweigh the bottle accurately. The difference gives the weight of pure iodine. Dilute the solution in the weighing bottle, and quickly transfer it quantitatively to a 250-ml measuring flask. Dilute upto the mark with distilled water. Stopper and keep in a dark place. The prepared solution is  $\frac{W \times 4}{126.91}$  N, where  $W$  is the weight of iodine dissolved. Make exactly N/10 by appropriate dilution.

*Oxalic acid (N/10)* : Dissolve 6.303 g of A.R. oxalic acid dihydrate  $\left[ \begin{array}{c} \text{COOH} \\ | \\ \text{COOH} \end{array} \right] \cdot 2\text{H}_2\text{O}$ , Mol. wt. 126.068, Eq. wt. 63.034] in boiled-out distilled water and dilute to 1 litre.

*Potassium dichromate (N/4)* : Dissolve 12.259 g of A.R.  $\text{K}_2\text{Cr}_2\text{O}_7$  (Mol. wt. 294.22, Eq. wt. 49.035), dried at  $100^\circ\text{C}$ , in boiled-out distilled water and dilute to 1 litre.

*Potassium dichromate (N/10)* : Prepare by appropriate dilution of the above solution.

*Potassium iodate (N/5)* : Dissolve 10.7 g of A.R.  $\text{KIO}_3$  (Mol. wt. 214.01, Eq. wt. 53.50 for Andrews titration) in boiled-out distilled water and dilute to 1 litre.

*Potassium iodate (N/10)* : Dissolve 3.567 g of A.R.  $\text{KIO}_3$  (Eq. wt. 35.67 for thiosulphate standardisation) in boiled-out distilled water and dilute to 1 litre.

*Potassium permanganate (N/10)* : Dissolve 3.2-3.25 g of A.R.  $\text{KMnO}_4$  (Mol. wt. 158.037, Eq. wt. 31.607) in 1 litre of distilled water. Boil for 1 hour and cool, or keep overnight. Filter through a plug of purified glass wool placed in the neck of a funnel or through sintered glass crucible (G-4) into a dark brown-coloured glass bottle. [Standardisation: 20 ml N/10 sodium oxalate solution + 100 ml of about 2N sulphuric acid. Warm to



50-60°C and titrate with potassium permanganate solution. Make exactly N/10 by appropriate dilution with water that has been redistilled from alkaline permanganate].

*Silver nitrate (N/20)* : Dissolve 8.4945 g of A.R.  $\text{AgNO}_3$  (Mol. wt. 169.89, Eq. wt. 169.89) in boiled-out distilled water and dilute to 1 litre.

*Silver nitrate (N/50)* : Prepare by appropriate dilution of the above solution with boiled-out distilled water.

*Sodium carbonate (N/2)* : Dissolve 13.25 g of A.R.  $\text{Na}_2\text{CO}_3$  (Mol. wt. 106, Eq. wt. 53), dried at 250°C, in boiled-out distilled water and dilute to 500 ml.

*Sodium carbonate (N/10)* : Dilute 50 ml of the above solution to 250 ml with boiled-out distilled water.

*Sodium carbonate (N/50)* : Prepare by appropriate dilution of N/2  $\text{Na}_2\text{CO}_3$  with boiled-out distilled water (10 ml to 250 ml).

*Sodium hydroxide (N/10)* : Dissolve 4-4.5 g of A.R.  $\text{NaOH}$  (Mol. wt. 40, Eq. wt. 40) pellets in 1 litre of boiled-out distilled water. Standardise with N/10 oxalic acid or against a known weight of potassium hydrogen phthalate ( $\text{KHC}_8\text{H}_4\text{O}_4$ , Mol. wt. 204.22, Eq. wt. 204.22) using phenolphthalein indicator. Make exactly N/10 by appropriate dilution with boiled-out distilled water.

*Sodium hydroxide (M/25)* : Prepare by appropriate dilution of the above solution with boiled-out distilled water.

*Sodium hydroxide (N/50)* : Prepare by appropriate dilution of N/10 sodium hydroxide solution with boiled-out distilled water.

*Sodium thiosulphate (N/10)* : Dissolve 25 g of A.R.  $\text{Na}_2\text{S}_2\text{O}_3 \cdot 5\text{H}_2\text{O}$  (Mol. wt. 248.21, Eq. wt. 248.21) in boiled-out distilled water and dilute to 1 litre. [Standardisation: 20 ml N/10  $\text{KIO}_3$  solution + 2 g A.R. KI and shake. Add 10 ml of 1N HCl and titrate against thiosulphate solution using starch solution as indicator near the end-point]. Make exactly N/10 by appropriate dilution

*Sodium thiosulphate (N/40)* : Prepare by appropriate dilution of the above solution with boiled-out distilled water.

*Sodium thiosulphate (N/100)* : Prepare by appropriate dilution of N/10 sodium thiosulphate solution with boiled-out distilled water.



*Sulphuric acid (N/2)* : Add slowly with constant stirring, 14 ml of concentrated A.R. sulphuric acid to a large volume of distilled water. Cool and dilute to 1 litre. Standardise with N/2  $\text{Na}_2\text{CO}_3$  using methyl orange indicator. Make exactly N/2 by appropriate dilution.

*Sulphuric acid (N/10)* : Dilute 3 ml of A.R. concentrated sulphuric acid to 1 litre in the way as above and standardise with N/10  $\text{Na}_2\text{CO}_3$  solution. Make exactly N/10 by appropriate dilution.

*Sulphuric acid (N/50)* : Prepare by appropriate dilution of the above solution.

### 1.6 Solutions of Approximate Strength

*Alcoholic potassium hydroxide (N/2)* : Dissolve 28 g of A.R. KOH (Eq. wt. 56) pellets in 1 litre of 95% alcohol (freshly distilled from KOH). Mix thoroughly and let stand undisturbed, for any carbonate to settle down. Decant the clear supernatant solution and use.

*Alkaline potassium iodide* : Dissolve 700 g of KOH pellets and 150 g of A.R. KI in distilled water and dilute to 1 litre.

*Aluminium sulphate (1.5% alum)* : Dissolve 15 g of  $\text{Al}_2(\text{SO}_4)_3 \cdot 18\text{H}_2\text{O}$  in 1 litre of distilled water.

*Ammonium molybdate (5%)* : Dissolve 50 g of ammonium heptamolybdate  $[(\text{NH}_4)_6\text{Mo}_7\text{O}_{24} \cdot 4\text{H}_2\text{O}]$  in 1 litre of warm distilled water. Cool and filter, if necessary.

*Ammonium oxalate (8%)* : Dissolve 80 g of ammonium oxalate monohydrate  $[(\text{NH}_4)_2\text{C}_2\text{O}_4 \cdot \text{H}_2\text{O}]$  in 1 litre of distilled water.

*Ammonium thiocyanate (10%)* : Dissolve 100 g of A.R.  $\text{NH}_4\text{SCN}$  in 1 litre of distilled water.

*Ammonium thiocyanate (N/20)* : Dissolve 3.8 g of A.R.  $\text{NH}_4\text{SCN}$  (Mol. wt. 76.11, Eq. wt. 76.11) in distilled water and dilute to 1 litre.

*Barium chloride (5%)* : Dissolve 50 g of  $\text{BaCl}_2 \cdot 2\text{H}_2\text{O}$  in 1 litre of distilled water.

*Bismuth chloride (0.1M)* : Dissolve 31.5 g of  $\text{BiCl}_3$  (Mol. wt. 315.5) in the minimum volume of 5N HCl and dilute to 1 litre. Add dropwise, with stirring, sufficient hydrochloric acid to remove any precipitate.

*Bromine solution (saturated)* : Prepare a saturated solution by shaking 11 ml of liquid bromine with 1 litre of distilled water.



*EDTA (N/50)* : Dissolve 3.723 g of disodium ethylene diaminetetra-acetate dihydrate (Mol. wt. 372.25, Eq. wt. 186.125) in one litre of distilled water.

*Ferric chloride (0.1M)* : Dissolve 27 g of  $\text{FeCl}_3 \cdot 6\text{H}_2\text{O}$  (Mol. wt. 270.5) in 1 litre of distilled water containing 50 ml of dilute HCl.

*Ferric nitrate (0.1M)* : Dissolve 40 g of  $\text{Fe}(\text{NO}_3)_3 \cdot 9\text{H}_2\text{O}$  (Mol. wt. 404) in 1 litre of distilled water containing 50 ml of dilute nitric acid.

*Ferric sulphate (0.5%)* : Dissolve 5 g of  $\text{Fe}_2(\text{SO}_4)_3$  (Mol. wt. 400) in 1 litre of distilled water.

*Ferrous sulphate (N/2)* : Dissolve 14 g of  $\text{FeSO}_4 \cdot 7\text{H}_2\text{O}$  (Mol. wt. 278, Eq. wt. 278) in 100 ml of distilled water containing 10 ml of dilute sulphuric acid.

*Hydrochloric acid (0.4 N)* : Dilute 36 ml of concentrated A.R. hydrochloric acid to 1 litre with distilled water.

*Iodic acid (N/10)* : Dissolve 3 g of iodic acid ( $\text{HIO}_3$ , Mol. wt. 176, Eq. wt. 29.33) in 1 litre of distilled water.

*Manganous sulphate (0.1 M)* : Dissolve 18.7 g of  $\text{MnSO}_4 \cdot 2\text{H}_2\text{O}$  (Mol. wt. 187) in distilled water. Filter and dilute to 1 litre.

*Manganous sulphate (48%)* : Dissolve 480 g of  $\text{MnSO}_4 \cdot 2\text{H}_2\text{O}$  in distilled water. Filter and dilute to 1 litre.

*Mercuric chloride (saturated)* : Dissolve 80 g of  $\text{HgCl}_2$  in 1 litre of hot distilled water. Cool to room temperature and filter.

*Oxalic acid (N/10)* : Dissolve 6.3 g of oxalic acid dihydrate in 1 litre of distilled water.

*Potassium iodide (0.1 M)* : Dissolve 16.6 g of iodate-free KI (Mol. wt. 166) in 1 litre of boiled-out distilled water.

*Potassium iodide (10%)* : Dissolve 100 g of iodate-free KI in 1 litre of boiled-out distilled water.

*Potassium oxalate (2%)* : Dissolve 20 g of potassium oxalate [ $\text{K}_2\text{C}_2\text{O}_4 \cdot \text{H}_2\text{O}$ ] in 1 litre of distilled water.

*Potassium permanganate (N/10)* : Dissolve 3.2 g of A.R.  $\text{KMnO}_4$  in 1 litre of distilled water. Boil for 1 hour, cool and filter through a plug of glass wool placed in the neck of a funnel into a dark-brown-coloured glass bottle.



*Potassium nitrate (0.1M)* : Dissolve 9.1 g of pure  $\text{KNO}_3$  (Mol. wt. 91) in 1 litre of distilled water.

*Potassium thiocyanate (0.1M)* : Dissolve 9.7 g of A.R.  $\text{KSCN}$  (Mol. wt. 97) in 1 litre of distilled water.

*Silver sulphate-sulphuric acid reagent* : Add 5.5 g of  $\text{Ag}_2\text{SO}_4$  crystals to 1 kg of  $\text{H}_2\text{SO}_4$  and let stand for 1-2 days for complete dissolution.

*Sodium bisulphite (N/20)* : Dissolve 2.6 g of  $\text{NaHSO}_3$  (Mol. wt. 104, Eq. wt. 52) in 1 litre of distilled water containing 50 ml of 2N  $\text{H}_2\text{SO}_4$ .

*Sodium thiosulphate (N/10)* : Dissolve 24.82 g of  $\text{Na}_2\text{S}_2\text{O}_3 \cdot 5\text{H}_2\text{O}$  (Mol. wt. 248.21, Eq. wt. 248.21) in 1 litre of boiled-out distilled water.

*Stannous chloride (0.1M)* : Dissolve 2.26 g of  $\text{SnCl}_2 \cdot 2\text{H}_2\text{O}$  (Mol. wt. 225.7) in 5-6 ml of concentrated hydrochloric acid and dilute to 100 ml.

*Stannous chloride (5%)* : Dissolve 50 g of  $\text{SnCl}_2 \cdot 2\text{H}_2\text{O}$  in 100 ml of concentrated hydrochloric acid and dilute to 1 litre.

*Sucrose (10%)* : Dissolve 100 g of granulated sugar in 1 litre of distilled water.

### 1.7 Titration Solvents for Acid Value of Oils

1. Mix together 500 ml toluene, 5 ml water and 495 ml isopropyl alcohol.
2. Mix together 500 ml chloroform, 5 ml water and 495 ml isopropyl alcohol.
3. Mix together equal volumes of ethyl alcohol and benzene.
4. Mix together equal volumes of alcohol and ether.
5. 95% alcohol—Add about 5 g of  $\text{KOH}$  to 1 litre of rectified spirit, boil for about half an hour and distil.
6. Pure distilled methyl alcohol.

### 1.8 Wij's Solution (0.2N solution of $\text{ICl}$ in glacial acetic acid)

1. Commercially available Wij's solution, which gives satisfactory results, may be used.
2. Dissolve 16 g of commercially available iodine monochloride ( $\text{ICl}$ ) in 1 litre of A.R. glacial acetic acid. Filter rapidly through a filter paper and store in amber-coloured glass-stoppered bottle in a dark place at a temperature below  $30^\circ \text{C}$ .
3. Dissolve 8 g of pure  $\text{ICl}_3$  (iodine trichloride) and 9 g of resublimed iodine separately in 500 ml of A.R. glacial acetic acid each. Warm on a water bath, if dissolution is not complete at room temperature. Add iodine solution gradually to  $\text{ICl}_3$  solution with constant shaking until a



red-brown colour appears. Add 20-30 ml more. Heat on a water bath for about 15 minutes, cool and store.

4. Shake to dissolve 13 g of resublimed iodine in 1 litre of A.R. glacial acetic acid. Titrate 10 ml of the solution with N/10  $\text{Na}_2\text{S}_2\text{O}_3$  and set aside another portion (20-30 ml). Pass chlorine gas (dried by bubbling through concentrated  $\text{H}_2\text{SO}_4$ ) into the remaining iodine solution until the volume of N/10  $\text{Na}_2\text{S}_2\text{O}_3$  used against 10 ml of the solution (after addition of 20 ml of 10% KI solution) is double the volume used before passing chlorine (Colour of the solution changes to orange at this stage). Neutralise any free chlorine with the original iodine solution. Heat on a water bath, cool and store.


### Exercises

1. What is a primary standard? Give some examples.
2. What is the general procedure for preparing a solution of definite normality (say N/10) of a substance which is not a primary standard?
3. 3.35 g of A.R. sodium oxalate (Eq. wt. 67) are dissolved in distilled water and diluted to 1 litre. 20 ml of this solution requires 19 ml of an unknown potassium permanganate solution for complete titration. Calculate the volume (in ml) of the unknown solution that should be diluted to 500 ml so as to get exactly N/20  $\text{KMnO}_4$  solution.
4. What are the advantages of using boiled-out distilled water, instead of ordinary distilled water, for the preparation of standard solutions?
5. How is sodium hydroxide solution freed of its carbonate content?
6. Explain why the permanganate solution should not be (a) filtered through a filter paper, (b) used in a clip-burette (with rubber tubing and pinch-cork)?




## Chemical Equilibrium and Chemical Kinetics


When a mixture of  $\text{CO(g)}$  and  $\text{NO}_2\text{(g)}$  is heated in a closed vessel, the reddish-brown colour of the mixture starts fading, indicating the progress of the following reaction :



However, if we take the colourless mixture of  $\text{CO}_2\text{(g)}$  and  $\text{NO(g)}$  [the products of reaction (2.1)] and heat, it is seen that the mixture slowly develops a reddish-brown colour due to the formation of  $\text{NO}_2\text{(g)}$  as per the following reaction :



which proceeds in a direction opposite to that of reaction (2.1). This is an example of a reversible reaction and is represented as :



A chemical reaction is said to be Reversible under defined experimental conditions if, under these conditions, the products of the reaction can react with one another to reform the original reactant or reactants.

### 2.1 Chemical Equilibrium


If the reaction mixture in the above example is heated to a constant temperature in a thermostatic bath, it is seen that the colour of the reaction mixture, which changes in the beginning, becomes constant after some time, indicating that the composition of the reaction mixture is no longer changing. The reaction is said to have reached equilibrium.

Chemical equilibrium, at a given temperature, is characterised by constancy of macroscopic properties—observable properties such as colour, pressure, concentration, density, etc.—in a closed system (a system containing a constant amount of matter) at a uniform temperature. Microscopic processes (changes at the molecular level), however, continue but in a balance that yields no macroscopic changes. Thus, both forward and backward reactions are proceeding simultaneously but at equal rates so that no change is observed.

Any factor that affects the rate of any one of the reactions involved in equilibrium will affect the conditions at equilibrium. Concentration, tempe-



rature and pressure are such factors. The effect of changes in any one of these factors on the equilibrium concentrations can be qualitatively predicted by applying the generalisation known as Le Chatelier's Principle—If a system at equilibrium is subjected to a change, the equilibrium shifts in a direction that tends to counteract partially the imposed change. The exact quantitative relationship between the concentrations of the reactants and the products at equilibrium is given by the Law of Chemical Equilibrium according to which the ratio of the product of the equilibrium concentrations of the substances formed to the product of the equilibrium concentrations of the reacting substances is constant at constant temperature. Thus, if [A] and [B] represent the molar concentrations of the reactants A and B, while [C] and [D] be the molar concentrations of the products C and D at equilibrium for the hypothetical reaction :



$$r_1, \text{ the rate of forward reaction} = k_1 [A] [B] \text{ and}$$

$$r_2, \text{ the rate of backward reaction} = k_2 [C] [D],$$

where  $k_1$  and  $k_2$  are constants.

At equilibrium

$$r_1 = r_2$$

$$\text{or } k_1 [A] [B] = k_2 [C] [D]$$

$$\text{or } \frac{[C] [D]}{[A] [B]} = \frac{k_1}{k_2} = K_c \quad (2.4)$$

$K_c$  is known as the concentration equilibrium constant and is constant at constant temperature. If its numerical value is determined by measuring the concentration of all the species in a particular equilibrium solution, it can be used in the calculations for any other equilibrium state between the same species at that same temperature.


2.1.1 *To study the effect of addition of solutions of  $Fe(NO_3)_3$ ,  $KSCN$ ,  $SnCl_2$  or  $KNO_3$  to the equilibrium system obtained by mixing aqueous solutions of  $Fe(NO_3)_3$  and  $KSCN$*

*Reagents required*


- (1) Ferric nitrate solution (0.1M)
- (2) Potassium thiocyanate solution (0.1M)
- (3) Stannous chloride solution (0.1M)
- (4) Potassium nitrate solution (0.1M)

*Theory*

When aqueous solutions of  $Fe(NO_3)_3$  and  $KSCN$  are mixed, the following three equilibria exist simultaneously:







(Pale yellow)    (Colourless)    (Reddish brown colour)

The equilibrium constant  $K_c$  for reaction (2.7) is given by

$$K_c = \frac{[\text{FeSCN}^{2+}]}{[\text{Fe}^{3+}][\text{SCN}^-]} \quad (2.8)$$

and remains constant at constant temperature, irrespective of the source of  $\text{Fe}^{3+}$ ,  $\text{SCN}^-$  and  $\text{FeSCN}^{2+}$  ions. Addition of any substance that will tend to change the concentration of any one of these ions will disturb (shift) the equilibrium in a particular way so that  $K_c$  may remain constant.

(a) *Addition of  $\text{Fe}(\text{NO}_3)_3$*  will increase the concentration of  $\text{Fe}^{3+}$  ions and in accordance with equation (2.8), in order to keep  $K_c$  constant, the concentration of  $\text{FeSCN}^{2+}$  should automatically increase which will be evidenced by deepening of the red colour.

(b) *Addition of  $\text{KSCN}$*  will increase the concentration of  $\text{SCN}^-$  and, in order that  $K_c$  may remain constant, more of  $\text{FeSCN}^{2+}$  will be formed which means that red colour will again deepen.

(c) *Addition of  $\text{SnCl}_2$*  will reduce  $\text{Fe}^{3+}$  ion to  $\text{Fe}^{2+}$ :



The consequent decrease in the concentration of  $\text{Fe}^{3+}$  will cause  $\text{FeSCN}^{2+}$  to dissociate so that  $K_c$  remains constant. Dissociation of  $\text{FeSCN}^{2+}$  will result in fading away of the reddish-brown colour.

(d) *Addition of  $\text{KNO}_3$*  will considerably increase the concentrations of  $\text{K}^+$  and  $\text{NO}_3^-$  ions, thus simultaneously depressing the dissociation of  $\text{Fe}(\text{NO}_3)_3$  and  $\text{KSCN}$  [reactions (2.5) and (2.6)] due to common ion effect. The resultant decrease in the concentrations of  $\text{Fe}^{3+}$  and  $\text{SCN}^-$  will make  $\text{FeSCN}^{2+}$  dissociate and the intensity of the colour will therefore decrease.

### Procedure

To about 40 ml of distilled water taken in a beaker, add 4 drops of  $\text{Fe}(\text{NO}_3)_3$  solution. Add  $\text{KSCN}$  solution dropwise with shaking until the solution acquires a light reddish-brown colour. Mix well and pour equal volumes of the solution into 5 clean test tubes. Mark the tubes as A, B, C, D and E and set aside tube A for colour comparison. Add 10 drops of the solution of  $\text{Fe}(\text{NO}_3)_3$  to tube B,  $\text{KSCN}$  to tube C,  $\text{SnCl}_2$  to tube D and  $\text{KNO}_3$  to tube E. After 2-3 minutes, compare the colours of solutions in tubes B, C, D and E with that of the solution in tube A, and record the observed changes in the intensity of the colour.




*Observations*

Tube	Initial colour	Solution added (10 drops)	Colour intensity
A	Reddish-brown	—	No change
B	-do-	$\text{Fe}(\text{NO}_3)_3$	Increases
C	-do-	KSCN	-do-
D	-do-	$\text{SnCl}_2$	Decreases
E	-do-	$\text{KNO}_3$	-do-

*Precautions*

- (i) Before pouring the reddish-brown solution into the test tubes, it should be well mixed so as to get a uniform concentration throughout.
- (ii) As far as possible, the temperature should be kept constant (a thermostat may be used).

2.1.2 To study the effect of addition of  $\text{H}_2\text{O}$  and  $\text{HCl}$  on the equilibrium represented by




and to show that the observations are in accord with Le Chatelier's Principle

*Reagents Required*

- (1) Bismuth chloride solution (0.1M).
- (2) Concentrated  $\text{HCl}$ .

*Theory*

The equilibrium constant  $K_c$  for the reaction



White precipitate

is given by

$$K_c = \frac{[\text{BiOCl}][\text{HCl}]^2}{[\text{BiCl}_3][\text{H}_2\text{O}]} \quad (2.11)$$

Addition of water will increase the denominator in the above expression. Therefore, in order to keep  $K_c$  constant, the numerator should also increase, i.e., the reaction (2.10) will proceed in the forward direction with the formation of more of  $\text{BiOCl}$  which will be indicated by an increase in the amount of white precipitate. Addition of a large excess of water will, in fact, lead to complete hydrolysis of  $\text{BiCl}_3$ . However, addition of  $\text{HCl}$  will increase the numerator in the expression (2.11). In order that  $K_c$  may remain constant,  $\text{BiOCl}$  will dissolve in  $\text{HCl}$  to increase the concentration of  $\text{BiCl}_3$ .



and water. In presence of a large excess of HCl, the reaction will go to completion in the backward direction, i.e., the whole of the precipitate of BiOCl will disappear.

### Procedure

To about 5 ml of BiCl<sub>3</sub> solution taken in a 100-ml beaker, add distilled water drop by drop, stirring throughout with a glass rod, until a white precipitate is observed. Continue the addition of water until an increase in the amount of white precipitate is no longer observed. Now add dropwise concentrated HCl, again stirring with a glass rod. Record the changes observed and continue the addition of HCl until the precipitate is completely dissolved. Again add water to observe the reversal of the changes.

### Observations


- (1) With the addition of more and more water, the amount of white precipitate goes on increasing.
- (2) With the addition of more and more of concentrated HCl, the amount of white precipitate goes on decreasing.

### Accord with Le Chatelier's Principle


By adding water, we tend to increase the concentration of one of the reactants. To reduce the effect of this change, the equilibrium shifts in the forward direction as evidenced by increase in the amount of precipitate. Similarly, addition of concentrated HCl tends to increase the concentration of one of the products. A portion of this HCl is utilised in dissolving BiOCl, thus partially counteracting the imposed change.

### Exercises

- 7.(a) Write down the expressions for  $K_c$  and  $K_p$  for the general reaction:
 
$$aA + bB + \dots \rightleftharpoons lL + mM + \dots \quad (2.12)$$
- (b) How are  $K_c$  and  $K_p$  related?
8. What specifically is 'equal' in a chemical reaction that has attained a state of equilibrium?
9. What is a steady state? With the help of an example, explain how it is different from chemical equilibrium.
- 10.(a) Using Le Chatelier's Principle, predict the effect of changing temperature on the equilibrium represented by the reaction:



- (b) What experiment would you perform to prove the above predictions?
11. What is the technological importance of Le Chatelier's Principle and Law of Chemical Equilibrium? Illustrate your answer by applying Le Chatelier's principle to the following equilibrium:





12. Giving examples, describe some ways in which equilibria, can be shifted to bring about essentially complete reactions.
13. Explain why  $\text{Cu}^{2+}$  and  $\text{Zn}^{2+}$  cannot be completely removed from industrial wastes by precipitation with  $\text{NH}_4\text{OH}$ ?
14. What is meant by an irreversible reaction? Give some examples.

## 2.2 Rate of a Reaction

Reactions proceed at different rates. The rate of a reaction refers to the amount of a reactant consumed or a product formed in a reaction in a definite unit of time. The quantity consumed or produced is expressed in concentration units (gram-moles per litre) if the substance is in solution, or in partial pressure units if the substance is a gas. The time may be expressed in microseconds for very rapid reactions such as explosion of household gas and oxygen; in seconds or minutes for reactions proceeding at moderate rates at room temperature such as decomposition of  $\text{H}_2\text{O}_2$  or oxidation of oxalic acid by permanganate; in days or months for slow reactions and in years for very slow reactions such as half-life period of  $^{226}_{88}\text{Ra}$  (1590 years).

### 2.2.1 Factors affecting the Rate of a Reaction

The rate of a reaction depends on a large number of factors such as

- (a) Concentration of the reactants,
- (b) Temperature of the system,
- (c) Nature of the reactants and the products,
- (d) Presence of a catalyst,
- (e) Surface area of the reactants, and
- (f) Exposure to radiation.

By a knowledge of how various factors influence the rate of a reaction, it becomes possible to bring the reaction under control, i.e., the speed of a reaction can be regulated to gain the desired effect. The economic viability of the process can therefore be ascertained.

#### (a) Effect of Concentration

This effect is best summarised in terms of the Law of Mass Action which states that "the rate at which a substance reacts is proportional to its 'active mass' and the rate of a chemical reaction is proportional to the product of the 'active masses' of the reacting substances". The active mass of solids is taken as unity and that of gases and solutions as the number of gram-moles present per litre.

A reaction between reacting molecules or ions can take place only when they come sufficiently close together. The rate of reaction will thus depend on the frequency with which the reacting particles collide (Collision Theory). The increase in concentration of one or more reactants by admitting their additional amounts (or by increasing the pressure in case of gaseous reactants) will increase the frequency of collision and is therefore expected to increase the rate of the reaction.




(b) *Effect of Temperature*

Rise in temperature causes only a slight increase in the frequency of molecular collisions (which are proportional to  $\sqrt{T}$ ) but experimental measurements indicate a manifold rise in the rate of reaction—A  $10^{\circ}\text{C}$  rise at room temperature causes about 1.5% increase in total number of binary collisions of HI molecules but the same change in temperature almost doubles the rate of dissociation.


*Explanation:* In a methane-oxygen mixture under ordinary conditions, although a methane molecule collides with an oxygen molecule a billion times in one second, there is no noticeable reaction. It has been postulated that a collision will result into a reaction only if the colliding particles possess an energy equal to or higher than a certain minimum (different for different reactions) known as the Threshold Energy. At room temperature, the number of such particles may constitute only a negligible fraction of the total number and thus the reaction may not be noticeable at all. However, even with a small rise in temperature, the number of particles having energy equal to or in excess of Threshold Energy increases appreciably, resulting in a large increase in the number of successful collisions.

(c) *Nature of Reactants* has a considerable influence on the rate of reaction. Under identical experimental conditions, reactions that involve considerable bond rearrangement (breaking of old bonds in the reactant molecules and formation of new ones in the product molecules) are expected to be slow while those that do not involve much bond rearrangement are expected to be fast.

Thus oxidation of NO by  $\text{O}_2$  which involves breaking of two bonds in



nitric oxide and formation of four bonds in nitrogen peroxide is much faster at room temperature than oxidation of methane with  $\text{O}_2$ , which involves breaking of four bonds in methane



and formation of six new bonds (2 in  $\text{CO}_2$  and 4 in  $2\text{H}_2\text{O}$ ).

(d) *Effect of presence of a Catalyst*

The additional energy that the reactant molecules having energy less than Threshold Energy must acquire so that their collision results in the formation of the products is known as Activation Energy.

$$\text{Activation Energy} = \text{Threshold Energy} - \text{Average Energy possessed by the molecules}$$

Addition of a catalyst provides a new reaction path with a lower energy barrier (Activation Energy). Since the energy barrier is reduced, a larger number of the molecules of the reactants can get over it (i.e., have energy equal to or higher than Threshold Energy) and consequently the rate of the reaction increases.



(e) *Surface Area of Reactants* has a bearing on the rate of a reaction taking place in a heterogeneous system (reaction between two solids, a solid and a liquid, two immiscible liquids, etc.) since reaction can take place only at the surface at which the reactants are in contact. Surface area for a given mass of a substance increases with decrease in particle size. Smaller particles, therefore, react more rapidly than larger particles. Thus, in air, coal dust burns much more rapidly than a large lump of coal.


### 2.2.2. To study the effect of Concentration and Temperature on the rate of reaction between iodic acid and sodium bisulphite

#### Reagents required


1. Iodic acid solution (N/10).
2. Sodium bisulphite solution (N/20).
3. Freshly prepared starch solution.

#### Theory

The reaction between iodic acid and bisulphite, which is carried out in presence of a small amount of freshly prepared starch solution to act as indicator, essentially consists of the following consecutive steps :



The iodine liberated in step (2.18) readily reacts with any unconsumed bisulphite present



and so no blue colour is observed. However, when step (2.17) has gone to completion, step (2.18) takes place almost instantaneously producing iodine which is evidenced by the appearance of characteristic blue-black colour. The sudden colour change thus indicates complete oxidation of bisulphite. The time elapsed, which is measured using a stop watch, between the mixing of the solutions of bisulphite and iodic acid and the sudden appearance of the blue-black colour is a measure of the rate of reaction.

#### Procedure

1. Take three 250-ml conical flasks and mark them as A, B and C.
2. With a measuring cylinder, pour 170 ml distilled water into flasks A and C and 160 ml distilled water into flask B.
3. Add with a pipet 20 ml of bisulphite solution to all the flasks.
4. Add 1 ml of freshly prepared starch solution to all the flasks.
5. With a pipet, add 10 ml of iodic acid solution to flask A, starting a stop-watch simultaneously. Mix and allow to stand at room temperature. Record the time when a blue-black colour appears.
6. Repeat the process with flask B, but adding 20 ml of iodic acid.



7. Add 10 ml of iodic acid to flask C, mix and keep the flask in a hot water bath and note the time for the development of blue colour.

### Observations

Flask	Vol. of H <sub>2</sub> O (ml)	Vol. of bisulphite (ml)	Vol. of HIO <sub>3</sub> (ml)	Temperature	Time in seconds
A	170	20	10	room temp	$t_1 =$
B	160	20	20	room temp	$t_2 =$
C	170	20	10	hot water bath	$t_3 =$

### Discussion of Results

1. Blue colour appears in flask B quicker than in flask A ( $t_2 < t_1$ ) because the reaction proceeds at a faster rate due to higher concentration of iodic acid in flask B.
2. Appearance of blue colour in flask C is quicker than in flask A ( $t_3 < t_1$ ) because the reaction is carried out at higher temperature which increases the rate of reaction.





### 2.2.3 To study the effect of nature of reactants on the rate of reaction

#### Reagents Required

1. Oxalic acid solution (N/10)
2. Ferrous sulphate solution (N/10)
3. Potassium permanganate solution (N/10)
4. Dilute H<sub>2</sub>SO<sub>4</sub>

#### Theory

KMnO<sub>4</sub> in acidic medium oxidises both ferrous ion and oxalate ion as per the following reactions :



As the permanganate ion is common to the two reactions, any difference in their rates will evidently be due to the difference in the specific characteristics of ferrous ion and oxalate ion. The rates of the two reactions are compared by noting the times required for decolourisation of equal amounts of acidified permanganate solution by equivalent amounts of ferrous ion and oxalate ion solutions at room temperature.



*Procedure*

- (1) Take two test tubes and mark them A and B.
- (2) Transfer with a graduated pipet 1 ml of oxalic acid solution to tube A and 1 ml of ferrous sulphate solution to tube B.
- (3) To 20 ml of distilled water taken in a beaker, add 5 ml of dilute  $\text{H}_2\text{SO}_4$  and 1 drop of  $\text{KMnO}_4$  solution and mix well.
- (4) Add 1 ml of the above diluted solution to each of the two test tubes A and B.
- (5) Allow to stand at room temperature and note the time needed for the purple colour of permanganate to disappear in the tubes A and B and record in the table.

*Observations*

Tube	Oxalic acid solution taken	Ferrous sulphate solution taken	$\text{KMnO}_4$ solution added	Decolourisation time in seconds
A	1 ml	—	1 ml	$t_1 =$
B	—	1 ml	1 ml	$t_2 =$

*Results and discussion*

The observations show that the colour of  $\text{KMnO}_4$  disappears much faster in the tube containing ferrous sulphate than in the tube containing oxalic acid ( $t_2 < t_1$ ). This is as expected since ferrous is a simple ion whereas oxalate is a polyatomic ion containing many covalent bonds that have to be broken.

### 2.2.4 To study the catalysing effect of $\text{Mn}^{2+}$ ions on the rate of reaction between oxalate and permanganate ions in acid medium

*Reagents required*

1. Oxalic acid solution (N/10)
2. Manganous sulphate solution (0.1M)
3. Potassium permanganate solution (N/10)
4. Dilute  $\text{H}_2\text{SO}_4$

*Theory*

Oxalate decolourises permanganate in acid medium (reaction 2.21). The time required is a measure of the rate of reaction. The effect of the presence of  $\text{Mn}^{2+}$  ions on the rate of reaction is seen by comparing the times needed for decolourisation in the absence and in the presence of  $\text{Mn}^{2+}$  ions. Other factors like the concentration of oxalate, permanganate and acid, and temperature are kept constant.



*Procedure*

- (1) Take two clean test tubes and mark them A and B.
- (2) Pour with a graduated pipet 1 ml of oxalic acid solution into each of the two tubes.
- (3) Add 1 ml of manganous sulphate solution to tube B.
- (4) Pour 1 ml of very dilute solution of acidified  $\text{KMnO}_4$  (as prepared in the previous experiment) into each of the tubes.
- (5) Shake the contents of the two tubes and allow to stand at room temperature.
- (6) Record the time needed for purple colour of  $\text{KMnO}_4$  to disappear in the two tubes.

*Observations*

Tube	Oxalic acid	$\text{KMnO}_4$	$\text{MnSO}_4$	Time for decolourisation (seconds)
A	1 ml	1 ml	-	$t_1 =$
B	1 ml	1 ml	1 ml	$t_2 =$

*Results and Discussion*

Observations indicate that  $t_2$  is less than  $t_1$ . Manganese (II) ions present in tube B catalyze the reaction between oxalate and permanganate ions (reaction 2.21) and so decolourisation of  $\text{KMnO}_4$  takes place at a faster rate in tube B.

2.2.5 *To study the effect of Surface Area on the rate of a reaction**Reagents Required*


1. Potassium thiocyanate solution (0.1M)
2. Ferric chloride solution (0.1M)
3. Dilute HCl
4. Steel wool
5. Iron nail

*Theory*

Addition of  $\text{FeCl}_3$  solution to the acidified solution of KCNS produces a reddish-brown colour :



The iron added reacts with HCl to produce nascent hydrogen which



reduces ferric to ferrous :





This decrease in the concentration of  $\text{Fe}^{3+}$  ions shifts the equilibrium (reaction 2.22) to left thus reducing the intensity of the colour.

### Procedure

Take 10-15 ml of dilute HCl in a beaker. Add 1 ml of KSCN solution and a drop of  $\text{FeCl}_3$ . A red colour appears. Add equal volumes of this solution to three clean test tubes. Mark them A, B and C and set aside tube A for colour comparison. Add a small wad of steel wool to the tube B and an iron nail to tube C. Set aside the tubes and observe their colour during the next 10 minutes.

### Observations

Tube	Initial colour	Physical state of iron added	Colour after 10 minutes
A	Reddish-brown	—	No change in colour intensity
B	-do-	Steel wool	Least intense colour
C	-do-	Iron nail	Less intense than A but more intense than B.

### Results and Discussion

The reddish-brown colour fades faster in tube B (to which steel wool has been added) than in tube C (to which iron nail is added). Because of the much larger surface area of steel wool than that of iron nail, rate of liberation of nascent hydrogen in tube B is higher which leads to faster rate of reduction of ferric ions and hence faster fading of the colour.

### Precautions

- (1) The weights of steel wool and iron nail should, as far as possible, be the same.

### Exercises

15. In experiment 2.2.2, why is 10 ml less water taken in flask B than in flasks A & C?
16. In the above experiment, what effect would you expect on the reaction time if more water is added to the reaction mixture at room temperature?
17. What is meant by the rate-determining step? Point out the rate-determining step in the reaction between  $\text{HIO}_3$  and  $\text{NaHSO}_3$  (Experiment 2.2.2).
18. What is meant by a clock reaction?
19. Explain why there is a danger of explosion in a saw mill?
20. Predict the observations when a few (8-10) crystals of KI and an equal

S.C.B.R.T. LIBRARY

Date

Accn No.

10.8.98

9690






amount of  $\text{HgCl}_2$  crystals are placed in a mortar and

- (i) Mixed with a glass rod.
  - (ii) Ground with a pestle.
  - (iii) About 10 ml distilled water is added to the above mixture, and
  - (iv) A concentrated solution of KI is then added while stirring with a glass rod.
21. Give some examples of reactions that are catalysed by radiation.
  22. Why does the rate of a reaction fall with time?
  23. Why is the speed of a reaction important?

### 2.3 Velocity Constant and Order of a Reaction

Consider the hypothetical reaction



The rate of this reaction at a particular temperature is given by the expression  $r = k[A]$ , called the rate equation, where  $[A]$  represents the molar concentration of the only reactant A and  $k$  is a constant characteristic of the reaction, and is known as the Rate Constant or the Velocity Constant of the reaction at the given temperature. If  $[A] = 1$ ,  $r = k$ . Thus at a given temperature, the rate constant or velocity constant of a reaction involving a single reactant is equal to the rate of the reaction when the molar concentration of the reactant is unity. It is also called the Specific Reaction Rate, and when multiplied by the concentration of the reactant at any instant gives the rate of the reaction at that instant. For a reaction involving more than one reactant, the Rate Constant is equal to the rate of the reaction when the concentration of each of the reactants is unity.


*Order of a Reaction* is equal to the sum of the powers of the concentration terms of the experimentally determined rate equation of a reaction. Thus a reaction is said to be of First Order if its experimentally determined rate can be represented by an expression of the type  $r = k \cdot C_A$ , and of Second Order if the rate can be expressed as  $r = k \cdot C_A^2$

$$\text{or } r = k \cdot C_A \cdot C_B$$

where  $C_A$  and  $C_B$  represent the molar concentrations of the reactants A and B, and so on.

#### 2.3.1 Kinetics of a First Order Reaction

Let the initial concentration of the reactant A for the reaction



be ' $a$ ' gram-moles/litre, out of which ' $x$ ' gram-moles/litre is converted into products in ' $t$ ' seconds. Thus after ' $t$ ' seconds from the start, the concentration of the reactant will be  $(a-x)$  gram-moles/litre and the rate of the reaction at this instant will be given by  $\frac{dx}{dt} = k(a-x)$ . Integrating this equation between



the time limits  $t = 0$  and  $t = t$ , and using the fact that when  $t = 0$ ,  $x = 0$ , we get

$$k = \frac{1}{t} \ln \frac{a}{a-x} = \frac{2.303}{t} \log \frac{a}{a-x} \quad (2.25)$$

If  $x_1$  and  $x_2$  be respectively the number of gram-moles/litre of the reactant changed into the products up to times  $t_1$  and  $t_2$  from the start, then the above equation takes the form

$$k = \frac{2.303}{t_2 - t_1} \log \frac{a-x_1}{a-x_2} \quad (2.26)$$


2.3.2 To determine the Rate Constant of hydrolysis of methyl acetate by dilute HCl and to show that it is a First Order reaction.

#### Reagents Required

1. Hydrochloric acid (0.4 N)
2. Sodium hydroxide solution (N/10)
3. Pure methyl acetate
4. Phenolphthalein indicator

#### Theory

The hydrolysis of methyl acetate in presence of an acid may be represented as



HCl merely acts as a catalyst and so its concentration, which remains constant throughout, will not affect the order of the reaction. Also, since water is present in large excess, its active mass (molar concentration) remains practically unchanged during the reaction. The rate of hydrolysis is therefore determined only by the concentration of methyl acetate :

$$r = \frac{dx}{dt} = k[\text{CH}_3\text{COOCH}_3] = k(a-x)$$

or

$$k = \frac{2.303}{t} \log \frac{a}{a-x} \quad (2.25)$$

$$= \frac{2.303}{t_2 - t_1} \log \frac{a-x_1}{a-x_2} \quad (2.26)$$

where  $x_1$  and  $x_2$  are the gram-moles/litre of methyl acetate hydrolysed at times  $t_1$  and  $t_2$  respectively from the beginning.

As acetic acid is produced on hydrolysis, the progress of the reaction is followed by withdrawing definite volumes of the reaction mixture at suitable time intervals and titrating against a standard alkali solution. The increase in the volume of alkali used is a measure of methyl acetate hydrolysed. If  $V_{t_1}$ ,  $V_{t_2}$  and  $V_\infty$  respectively be the volumes of standard alkali used against the



same definite volume of the reaction mixture at times  $t_1$ ,  $t_2$  and  $t_\infty$  (the time required for the reaction to be completed), then

$V_{t_1} \propto$  amount of HCl present originally + amount of acetic acid formed or methylacetate hydrolysed at time  $t_1$  ( $x_1$ ),

and  $V_\infty \propto$  amount of HCl present originally + amount of  $\text{CH}_3\text{COOH}$  formed at the end of reaction or initial concentration of methyl acetate ( $a$ ).

Therefore,  $V_\infty - V_{t_1} \propto (a - x_1)$  i.e. the concentration of unhydrolysed  $\text{CH}_3\text{COOCH}_3$  at time  $t_1$ .

Similarly,  $V_\infty - V_{t_2} \propto (a - x_2)$ , i.e. the concentration of unhydrolysed  $\text{CH}_3\text{COOCH}_3$  at time  $t_2$ .

Therefore, equation (2.26) can be written as

$$k = \frac{2.303}{t_2 - t_1} \log \frac{V_\infty - V_{t_1}}{V_\infty - V_{t_2}} \quad (2.28)$$

#### Procedure

- (1) Take about 100 ml of the HCl solution in a clean conical flask and suspend it in a thermostat maintained at  $25^\circ\text{C}$ . Take about 15 ml of pure methylacetate in a clean dry tube, cork it and suspend in the same thermostat.
- (2) Take 8 conical flasks, each of 100-ml capacity; pour about 25 ml of distilled water into each and keep them immersed in an ice-water bath.
- (3) Wash a burette and rinse and fill it with NaOH solution.
- (4) When the two liquids (methyl acetate and HCl) have attained the temperature of the bath, pipet out 10 ml of methyl acetate and pour it into the acid contained in the flask.
- (5) Mix by shaking and pipet out 5 ml of the reaction mixture into one of the flasks containing 25 ml of ice-cold water, starting a stop watch when the pipet has been half discharged. Add 1 drop of phenolphthalein indicator to this solution and titrate quickly with NaOH solution until a pink colour appears. Record the titre value as  $V_t$ . Time for this value is zero.
- (6) Similarly, withdraw 5-ml portions of the reaction mixture at times 5, 10, 20, 30, 50 and 80 minutes and pour into flasks containing 25 ml of ice-cold water and titrate quickly against the same alkali solution.
- (7) For finding  $V_\infty$ , transfer about 20 ml of the reaction mixture to a clean dry flask, stopper it tightly and keep immersed in a water bath maintained at  $50^\circ\text{C}$  for 80-90 minutes so as to complete the hydrolysis. Cool to room temperature. Pipet out 5 ml of the solution to a flask containing 25 ml of ice-cold water and titrate as before.

#### Precautions

- (1) As the rate of reaction is very sensitive to temperature changes, the temperature of the bath should be maintained constant within  $\pm 0.5^\circ\text{C}$  throughout the course of the experiment.
- (2) For every titration, the time should be recorded when the pipet has been half discharged into the flask.



- (3) The titration should be made as quickly as possible—for this the bulk of the expected volume of alkali should be run in quickly and then there should be dropwise addition to the first appearance of pink colour that persists for at least 10 seconds.

### Observations and Calculations

Temperature of the bath =  $t^{\circ}\text{C}$

Time in min $t$	Titre value $V_t$ ml	Concentration of unhydrolysed $\text{CH}_3\text{COOCH}_3$ at time $t$ ( $V_{\infty} - V_t$ )	$\log(V_{\infty} - V_t) \quad k = \frac{2.303}{t_2 - t_1} \log \frac{V_{\infty} - V_{t_1}}{V_{\infty} - V_{t_2}}$
$t_0 =$	$V_{t_0} =$	$V_{\infty} - V_{t_0}$	
$t_1 =$	$V_{t_1} =$	$V_{\infty} - V_{t_1}$	
$t_2 =$	$V_{t_2} =$	$V_{\infty} - V_{t_2}$	
$t_3 =$	$V_{t_3} =$	$V_{\infty} - V_{t_3}$	
$t_4 =$	$V_{t_4} =$	$V_{\infty} - V_{t_4}$	
$t_5 =$	$V_{t_5} =$	$V_{\infty} - V_{t_5}$	
$t_6 =$	$V_{t_6} =$	$V_{\infty} - V_{t_6}$	
$t_{\infty}$	$V_{\infty} =$		

### Results and Discussion

- (1) Since the values of  $k$ , as calculated by substituting the various values of  $V_{\infty} - V_t$  for the corresponding  $t$  values in the kinetic equation for first order, i.e.,

$$k = \frac{2.303}{t_2 - t_1} \log \frac{V_{\infty} - V_{t_1}}{V_{\infty} - V_{t_2}}$$

remain almost constant, the hydrolysis of methyl acetate catalysed by acid is a first order reaction.

- (2) The average of the various values of  $k$  is the velocity constant of the reaction at the temperature of the experiment.

### Graphical Method

The rate equation for the first order reaction

$$\begin{aligned} t &= \frac{2.303}{k} \log \frac{a}{a-x} \\ &= \frac{2.303}{k} \log a - \frac{2.303}{k} \log (a-x) \\ &= \text{constant} - \frac{2.303}{k} \log (a-x) \end{aligned} \quad (2.29)$$



indicates that a plot of  $t$  against  $\log (a - x)$  or  $\log (V_{\infty} - V_t)$  will be a straight line whose slope is given by  $-\frac{2.303}{k}$

Thus 
$$-\frac{2.303}{k} = \tan \theta = -\frac{OA}{OB}$$

or 
$$k = 2.303 \times \frac{OB}{OA}$$




Fig. 1 Plot of  $t$  versus  $\log (V_{\infty} - V_t)$ .

2.3.3 To compare the Strengths of  $HCl$  and  $H_2SO_4$  by studying their catalysing action on hydrolysis of methyl acetate.

#### Reagents Required

1. Standard hydrochloric acid (N/2)
2. Standard sulphuric acid (N/2)
3. Sodium hydroxide solution (N/10)
4. Pure methyl acetate
5. Phenolphthalein indicator

#### Theory

The hydrolysis of methyl acetate is catalysed by an acid (reaction 2.27) and the rate of hydrolysis is found to be approximately proportional to the concentration or more correctly activity of  $H^+$  ions. Therefore, the velocity constants of the reaction in presence of equal concentrations (equinormal solutions) of two acids will be proportional to their degrees of dissociation or their strengths:

$$\text{Relative strengths} = \frac{\text{Strength of } HCl}{\text{Strength of } H_2SO_4} = \frac{\alpha_1}{\alpha_2} = \frac{k_1}{k_2} \quad (2.30)$$



where  $\alpha_1$  and  $\alpha_2$  are the degrees of dissociation of HCl and  $\text{H}_2\text{SO}_4$  and  $k_1$  and  $k_2$  are the velocity constants of the hydrolysis of methyl acetate in presence of their equinormal solutions.

#### Procedure

- (1) Determine the velocity constant  $k_1$  of the hydrolysis of methyl acetate by taking exactly 100 ml of N/2 HCl (standard), at a definite temperature maintained by means of a thermostat, as described in the earlier experiment.
- (2) In the same way, determine the velocity constant  $k_2$  by taking exactly 100 ml of N/2  $\text{H}_2\text{SO}_4$  (standard) and the same exact amount of methyl acetate, and carrying out the reaction at the same temperature as above.
- (3) The ratio  $k_1/k_2$  gives the relative strength of HCl and  $\text{H}_2\text{SO}_4$ .

#### Precautions

1. The conical flasks in which HCl and  $\text{H}_2\text{SO}_4$  are taken should be clean and dry.
2. The two acid solutions must be exactly equinormal.
3. The temperature should be maintained constant throughout the course of the two determinations.

*2.3.4 To determine the Temperature Coefficient of hydrolysis of methyl acetate by acid and to calculate the Energy of Activation of the reaction*

#### Reagents Required

1. Hydrochloric acid (N/2)
2. Sodium hydroxide solution (N/10)
3. Pure methyl acetate
4. Phenolphthalein indicator solution

#### Theory

As discussed earlier (p. 16), a rise in temperature markedly increases the rate of a reaction. The ratio of the velocity constants of a reaction at two temperatures differing by  $10^\circ\text{C}$  is known as temperature coefficient of the reaction. The temperatures usually selected are  $25^\circ\text{C}$  and  $35^\circ\text{C}$  and the value of the temperature coefficient for a majority of the reactions varies from 2 to 3.

$$\begin{aligned}\text{Temperature coefficient} &= \frac{\text{Velocity constant at } 35^\circ\text{C}}{\text{Velocity constant at } 25^\circ\text{C}} \\ &= \frac{k_{35}}{k_{25}} \approx 2 \text{ to } 3\end{aligned}\quad (2.31)$$

The temperature coefficient usually decreases with rise in temperature. The



variation of velocity constant with temperature is best expressed by the following empirical equation proposed by Arrhenius:

$$k = A \exp(-E_a/RT) \quad (2.32)$$

where  $A$  = a constant;  $E_a$  = Energy of activation;  $R$  = Gas constant and  $T$  = Absolute temperature.

Taking logarithms

$$\ln k = -\frac{E_a}{RT} + \ln A$$

(constant)

If  $k_1$  and  $k_2$  be the velocity constants of the reaction at temperatures  $T_1^\circ \text{K}$  and  $T_2^\circ \text{K}$ , respectively, then assuming  $E_a$  to be independent of temperature,

$$\ln k_2 - \ln k_1 = -\frac{E_a}{R} \left[ \frac{1}{T_2} - \frac{1}{T_1} \right]$$

or

$$\ln \frac{k_2}{k_1} = -\frac{E_a}{R} \left[ \frac{1}{T_2} - \frac{1}{T_1} \right]$$

or

$$\log \frac{k_2}{k_1} = \frac{E_a}{2.303R} \left[ \frac{1}{T_1} - \frac{1}{T_2} \right] \quad (2.33)$$

Thus, by measuring velocity constants  $k_1$  and  $k_2$  of the hydrolysis of methyl acetate at two different temperatures  $T_1$  and  $T_2$ , and substituting the values in the above equation,  $E_a$ , the Energy of Activation for the reaction can be calculated.

#### Procedure

- (1) Determine the velocity constant  $k_{25}$  for the hydrolysis of methyl acetate catalysed by HCl, at a temperature of  $25^\circ\text{C}$  ( $298^\circ\text{K}$ ) maintained by a thermostat, as described in experiment 2.3.2.
- (2) Determine the velocity constant  $k_{35}$  for the hydrolysis of methyl acetate, by taking exactly the same amounts of HCl and methyl acetate as in (1) above, at a temperature of  $35^\circ\text{C}$  ( $308^\circ\text{K}$ ) maintained with the help of a thermostat.
- (3) Calculate the ratio  $\frac{k_{35}}{k_{25}}$  and report as temperature coefficient of the hydrolysis of methyl acetate catalysed by acid.
- (4) Substitute the values of  $k_{35}$ ,  $k_{25}$ ,  $T_1$  ( $298^\circ\text{K}$ ),  $T_2$  ( $308^\circ\text{K}$ ) and  $R = 2 \text{ cal/degree/mole}$  or  $8.314 \text{ joules/K/mole}$  in the expression

$$\log \frac{k_{35}}{k_{25}} = \frac{E_a}{2.303R} \left[ \frac{1}{T_1} - \frac{1}{T_2} \right] \quad (2.34)$$

and calculate the value of  $E_a$ .



**Exercises**

24. Why is the reaction mixture dropped into ice-cold water before titration ?
25. Give some examples of First Order Reactions.
26. What is meant by molecularity of a reaction ? How is it different from order of the reaction ?

**2.3.5 Kinetics of a Second Order Reaction**

A second order reaction in which there is only one reactant is represented by  $2A \rightarrow \text{Products}$ . Let 'a' gram-moles/litre be the initial concentration of A, out of which 'x' gram-moles/litre is converted into products in 't' minutes. Thus after t minutes from the start, the concentration of the reactant will be (a-x) gram-moles/litre, and the rate of reaction at this instant will be given by

$$\frac{dx}{dt} = k(a-x)^2$$

Integrating this equation between the limits  $t = 0$  and  $t = t$ , and using the fact that when  $t = 0$ ,  $x = 0$ , we get

$$k = \frac{1}{at} \cdot \frac{x}{(a-x)} \quad (2.35)$$

The above equation can be rearranged to give

$$\frac{1}{(a-x)} = kt + \frac{1}{a} \quad (2.36)$$

If the reaction involves two different reactants, i.e.,  $A + B \rightarrow \text{Products}$ , but both the reactants have the same initial concentration — 'a' gram-moles/litre—the rate constant  $k$  is given by equation (2.35). If, however, the initial concentration of A and B is 'a' gram-moles/litre and 'b' gram-moles/litre, respectively, the rate equation will be  $\frac{dx}{dt} = k(a-x)(b-x)$  and the rate constant will be given by

$$k = \frac{2.303}{t(a-b)} \log \frac{b(a-x)}{a(b-x)} \quad (2.37)$$

In the expressions for  $k$  (2.35 or 2.37), there is one additional concentration term in the denominator. Hence, the value of the second order rate constant depends on the units in which the concentration of the reactants is expressed. If the concentration is expressed in moles/litre and the time in minutes, the units of  $k$  will be  $(\text{moles/litre})^{-1} \text{ minute}^{-1}$ .

**2.3.6. To determine the Rate Constant of hydrolysis of ethyl acetate by NaOH (saponification) and to show that it is a Second Order reaction**

**Reagents Required**


1. Standard ethyl acetate solution (M/25)
2. Standard sodium hydroxide solution (M/25)



3. Standard sodium hydroxide solution (M/50)
4. Standard hydrochloric acid (M/50)
5. Phenolphthalein indicator solution

*Theory*

The hydrolysis of ethyl acetate by sodium hydroxide, also known as saponification of ethyl acetate, may be represented as



The rate of saponification may be represented by

$$\begin{aligned} \gamma = \frac{dx}{dt} &= k [\text{CH}_3\text{COOC}_2\text{H}_5] [\text{OH}^-] \\ &= k(a-x)^2, \end{aligned}$$

when the initial concentration of both ethyl acetate and sodium hydroxide is 'a' gram-moles/litre and 'x' gram-moles/litre of each reacts in time *t*. The rate constant *k* is then given by equation (2.35):

$$k = \frac{1}{at} \cdot \frac{x}{(a-x)}$$

As one mole of sodium hydroxide is consumed for every mole of ethyl acetate hydrolysed, the progress of the reaction is followed by withdrawing definite fixed volumes of the reaction mixture at suitable time intervals and determining the amount of residual alkali.

*Procedure*

- (1) Take 50 ml (with a pipet) of M/25 ethyl acetate solution and 70-80 ml of M/25 NaOH in separate clean and dry 250-ml conical flasks. Stopper the flasks and suspend in a thermostat maintained at 25°C.
- (2) Take 6 conical flasks each of 100 ml capacity. Pour with a pipet, 20 ml of M/50 HCl into each flask and immerse in ice-water bath.
- (3) Wash a burette and rinse and fill it with M/50 NaOH.
- (4) When the two liquids (M/25 ethyl acetate and M/25 NaOH) have attained the temperature of the bath, pipet out 50 ml of sodium hydroxide solution. Pour this solution into the flask containing ethyl acetate solution, starting a stop watch when the pipet has been half discharged. This should be taken as zero time.
- (5) Immediately mix by shaking and after 5 minutes from the start, withdraw 10 ml of the reaction mixture and pour it into one of the flasks containing 20 ml of ice-cold M/50 HCl. Record the time when the pipet has been half discharged into the flask. Take this as the time *t*<sub>1</sub> of arresting the reaction.
- (6) Immediately add 2 drops of phenolphthalein indicator and titrate quickly against M/50 NaOH solution until a pink colour appears. Record the titre value as *V*<sub>1</sub>.



- (7) Similarly, withdraw 10-ml portions of the reaction mixture at times 10, 20, 30, 50 and 80 minutes and pour into flasks containing 20 ml of ice-cold HCl and titrate quickly against the standard (M/50) alkali solution. Record the titre values as  $V_{12}$ ,  $V_{13}$ ,  $V_{14}$ ,  $V_{15}$  and  $V_{16}$ , respectively.
- (8) As the reaction advances, the amount of residual alkali decreases and so the volume of M/50 NaOH required to back titrate the excess of acid increases and will approach 20 ml when the saponification reaction is complete.

### Precautions

1. As the rate of reaction is very sensitive to temperature changes, the temperature of the bath should be maintained constant within  $\pm 0.5^\circ\text{C}$  throughout the course of the experiment.
2. For every titration, the time should be recorded when the pipet has been half discharged into the flask.
3. The titration should be made as quickly as possible—for this the bulk of the expected volume of alkali should be run in quickly and then there should be dropwise addition to the first appearance of pink colour that persists for at least 10 seconds.

### Observations and Calculations

Temperature of the bath  $= t^\circ\text{C}$   
 Volume of M/25 ethyl acetate taken  $= 50\text{ ml}$   
 Volume of M/25 NaOH taken  $= 50\text{ ml}$   
 Total volume of the reaction mixture  $= 100\text{ ml}$   
 Therefore, 'a' the initial concentration of ethyl acetate

or NaOH in the reaction mixture  $= \text{M}/25 \times \frac{50}{100}$   
 $= \text{M}/50$

Volume of reaction mixture withdrawn  $= 10\text{ ml}$   
 Volume of M/50 HCl added  $= 20\text{ ml}$

Time in min, $t$	Titre value $V_t$ (ml)	$k = \frac{1}{at} \cdot \frac{V_t - 10}{20 - V_t}$ (moles/litre) $^{-1}$ min $^{-1}$	$(a-x) = \frac{20 - V_t}{500}$	$\frac{1}{(a-x)}$	$k = \tan \theta$
$t_1 =$	$V_{t_1} =$				
$t_2 =$	$V_{t_2} =$				
$t_3 =$	$V_{t_3} =$				
$t_4 =$	$V_{t_4} =$				
$t_5 =$	$V_{t_5} =$				
$t_6 =$	$V_{t_6} =$				



Let the volume of M/50 NaOH needed, after  $t$  minutes from the start, to back titrate excess acid  $= V_t$  ml.

$$V_t \text{ ml M/50 NaOH} \equiv V_t \text{ ml M/50 HCl}$$

Therefore, excess acid  $\equiv V_t$  ml of M/50 NaOH

Acid used for residual NaOH in 10 ml of the reaction mixture  $\equiv (20 - V_t)$  ml of M/50 NaOH

Residual concentration of NaOH in the reaction mixture at time  $t = \frac{(20 - V_t)}{10} \times \text{M/50}$

Thus  $(a - x)$  at time  $t = \left( \frac{20 - V_t}{500} \right) \text{M}$

Therefore,  $x = \left[ \frac{1}{50} - \frac{20 - V_t}{500} \right] \text{M} = \left( \frac{V_t - 10}{500} \right) \text{M}$

$$\begin{aligned} \text{and} \quad \frac{x}{a - x} &= \frac{V_t - 10}{500} \div \frac{20 - V_t}{500} \\ &= \frac{V_t - 10}{20 - V_t} \end{aligned} \quad (2.39)$$

Substituting  $\frac{V_t - 10}{20 - V_t}$  for  $\frac{x}{a - x}$  in equation (2.35), we get

$$k = \frac{1}{at} \cdot \frac{V_t - 10}{20 - V_t} \quad (2.40)$$

where  $a$

$$= \text{M/50.}$$

### Results and Discussion

1. Since the values of  $k$ , as calculated by substituting the various values of  $V_t$  for the corresponding  $t$  values in the equation (2.40) (the kinetic equation for second order), remain almost constant, the saponification of ethyl acetate is a second order reaction.

2. The average of various values of  $k$  is the velocity constant or rate constant of the saponification at the temperature of the experiment.

### Graphical Method

The rate equation (2.36) for the second order reaction indicates that a

$$\frac{1}{a - x} = kt + \frac{1}{a}$$

plot of  $\frac{1}{a - x}$  against  $t$  will be a straight line whose slope ( $\tan \theta$ ) gives the value  $k$ :

$$k = \tan \theta = \frac{BC}{AB} \quad (2.41)$$






Fig. 2 Plot of  $\frac{1}{a-x}$  versus  $t$

### Exercises

27. In experiment 2.3.6, why is the reaction mixture poured into ice-cold HCl before titration?
28. (a) Under what experimental condition will a reaction between two reactants be of first order?  
(b) Can you arrive at the same result mathematically?
29. Give some examples of second order reactions.
30. Write the expression for the rate constant of a third order reaction starting with equal concentration of all the reactants.
31. Why are Third or Higher Order Reactions very rare?
32. Give some examples of Third Order Reactions and one example of a Fourth Order Reaction.
33. Can the order of a reaction be zero? If so, give some examples.
34. What is meant by half-life period of a reaction?
35. What is the relationship between the half-life period of a reaction and the initial concentration of the reactant (s)?
36. Outline the usefulness of the study of chemical kinetics.
37. Giving one example, explain, how measuring the order of a reaction helps in understanding its mechanism.



---

## Water

Water is one of the most essential substances needed to sustain human life, animals and plants. It is needed for drinking, cooking, bathing, washing (cleansing), for sanitary disposal of domestic and human wastes, and for agriculture. It is also one of the most important engineering materials and is used for steam generation, as a coolant in power plants, for air-conditioning and fire-fighting, and in building and other concrete constructions. Water has a unique position in industry. It is needed for the production of such a wide variety of materials as steel and other metals, paper, textiles, beverages, dairy products, petroleum and coal, rubber and plastics, automobile industry, and as a solvent in chemical processing. In fact, production units not using water for some purpose or the other may be hard to find. It is for this reason that before setting up a production unit at a particular site, the quantity of water needed, the character and quality of water available and the effect of impurities in water on the process must be considered.

Although available in abundance, water from almost all the sources is associated with some kind of impurities; their nature and amount varying with the source of water. *Rain water*, the purest form of natural water, usually contains dust particles and gases dissolved from atmosphere, such as  $O_2$ ,  $N_2$ ,  $CO_2$  (ammonium salts,  $H_2S$  or  $H_2SO_4$  may be present in rain waters in industrial areas). *Surface waters* (from rivers, ponds, etc.) are usually rich in turbidity, suspended impurities of decaying organic matter (vegetable and/or animal), sand and finely divided clay, micro-organisms and bacteria, and small amounts of mineral salts (mainly  $Ca^{2+}$ ,  $Mg^{2+}$ ,  $Na^+$ ,  $SO_4^{2-}$ ,  $Cl^-$ , etc.) dissolved from top soil. *Underground waters* (from springs, wells or boreholes) usually contain negligible amounts of suspended and organic impurities (removed while passing through sand layers in earth) but may contain appreciable amounts of mineral impurities ( $Ca^{2+}$ ,  $Mg^{2+}$ ,  $K^+$ ,  $Na^+$ ,  $Fe^{2+}$ ,  $Al^{3+}$ ,  $Mn^{2+}$ ,  $HCO_3^-$ ,  $CO_3^{2-}$ ,  $SO_4^{2-}$ ,  $Cl^-$ ,  $NO_3^-$ , finely divided clay, etc.) brought into solution due to disintegration of mineral deposits and insoluble carbonate or aluminosilicate rocks by the combined action of high underground temperature, hydration, dissolved  $O_2$  and  $CO_2$ , and organic acids produced by aerobic and/or anaerobic decay of organic matter with which water has been in contact. *Sea water* is highly impure, containing around 3.5% dissolved minerals of which about 2.6% is  $NaCl$ .

Use of impure waters often leads to many problems like health complications, decrease in the efficiency of plants, increased cost, etc. However, of the wide range of impurities present, only a few may affect a particular process.



Therefore, removal or reduction in the concentration of only these impurities is necessary; the rest of the impurities which do not adversely affect the process may be allowed to remain as such. For example, water for laundries should be soft and free from colour; water for steam generation should be free from all dissolved solids and dissolved corrosive gases but removal of bacteria is not required. Specifications for drinking water are much more stringent with respect to the presence of pathogenic bacteria and certain toxic substances (Phenols  $< 0.005$  ppm; As, Cr, Pb, Ag, Mn  $< 0.05$  ppm; Cd, Se, cyanide  $< 0.01$  ppm; etc.) but may contain large amounts of substances like  $\text{Ca}^{2+}$ ,  $\text{Mg}^{2+}$ ,  $\text{Na}^+$ ,  $\text{K}^+$ ,  $\text{Cl}^-$ ,  $\text{SO}_4^{2-}$ , etc.



The treatment methods depend on the nature and amount of impurities present, which can be determined by analysis. A complete analysis, however, is usually not done. The extent of analysis is governed by the purpose for which water is to be used and the specifications laid down for the purpose. Analysis of the treated water is also carried out to compare the efficacy of different treatment processes and to choose the most efficient and economical process.

With the rapid growth in population, improvement in living standards and proliferation of industry, the demand for adequate supplies of suitable waters is increasing. So the water used in most of the industries and in sanitary disposal of human and domestic wastes, the water which is not actually consumed but is polluted, has to be reused. The treatment methods for recycling and reusing water have to depend on the nature and extent of contamination and pollution which can be determined by analysing the used water. A few of the routine tests that are carried out on water and waste water are discussed in the following pages.

### 3.1 Acidity and Alkalinity of Water

The acidity of a water sample is its capacity to neutralise a base whereas its alkalinity is a measure of its capacity to neutralise acids. Natural waters may be acidic or alkaline, depending upon the source of water and the extent and nature of pollutants from industry and municipal sanitary disposal.


Most natural waters contain dissolved  $\text{CO}_2$ . It may enter water by absorption from atmosphere or may be produced by biological oxidation of organic matter with which water has been in contact, e.g.,




$\text{CO}_2$  content of surface waters is normally much less than 10 mg/l but some ground waters may contain between 30 to 50 mg/l of  $\text{CO}_2$ . When waters containing high concentration of  $\text{CO}_2$  are exposed to atmosphere, most of  $\text{CO}_2$  escapes from the solutions as the partial pressure of  $\text{CO}_2$  in atmosphere is normally much less.

Waters may be acidic due to the presence of  $\text{CO}_2$  and/or organic acids formed by the decay of organic matter, e.g.,







Acidity may also arise due to the presence of mineral acids produced by the hydrolysis of salts of certain heavy metals such as  $\text{FeCl}_3$  or  $\text{Al}_2(\text{SO}_4)_3$ :



Waters may be alkaline due to the presence of a wide variety of salts of weak acids such as carbonates, bicarbonates, borates, silicates, phosphates, etc., and also due to the presence of weak and strong bases (due to contamination with industrial wastes). The major portion of alkalinity in natural water is, however, caused by presence of bicarbonates that are formed in appreciable amounts when water containing free  $\text{CO}_2$  percolates through soils containing  $\text{CaCO}_3$  and/or  $\text{MgCO}_3$ :



Waters softened by lime-soda process always contain excess amounts of carbonate and hydroxide, added to ensure complete precipitation of calcium and magnesium. Waters in which algae are present contain appreciable amounts of carbonate and hydroxide as algae remove both free and combined  $\text{CO}_2$ :



With borates, silicates and phosphates making only an insignificant contribution, the alkalinity of natural waters may be taken as an indication of the concentration of (i) Hydroxides, (ii) Carbonates, and (iii) Bicarbonates.

### 3.1.1 Determination of Free $\text{CO}_2$ in a sample of water

#### Significance

The  $\text{CO}_2$  content of a water sample is important as it contributes to corrosion. When present in boiler-feed water, it may cause corrosion of even those parts that lie at a distance from the boiler, such as superheater or the blades of steam turbines. In lime-soda process of water-softening, measurement of free  $\text{CO}_2$  is necessary for calculating additional amounts of lime to be added. Because of its corrosive nature and the unacceptable taste it imparts to water,  $\text{CO}_2$  is to be removed from municipal water supplies by aeration or by neutralisation with lime; the choice of the method depending upon the amounts of free  $\text{CO}_2$  present in the sample.




*Reagents Required*

1. Standard  $\text{Na}_2\text{CO}_3$  solution (N/50)
2. Phenolphthalein indicator solution.

*Theory*

Free  $\text{CO}_2$  can be determined by titrating with a standard solution of  $\text{NaOH}$  or  $\text{Na}_2\text{CO}_3$  with which it reacts to give  $\text{NaHCO}_3$ :



Phenolphthalein is used as indicator and titration is carried to pH 8.3 indicated by the appearance of pink colour.

*Procedure*

Collect a water sample in a 100-ml graduated cylinder by means of a submerged rubber tubing. To remove air bubbles, allow the sample to overflow for sometime. Remove the excess of the sample with the help of a pipet and adjust the level to 100-ml mark. Add 5 drops of the phenolphthalein indicator (appearance of pink colour indicates absence of  $\text{CO}_2$ ) and titrate against N/50  $\text{Na}_2\text{CO}_3$  solution until the pink colour persists for at least 30 seconds. Take concordant readings and record the volume used as A ml.

*Precautions*

1. To minimise the loss of  $\text{CO}_2$ 
  - (a) The titration should be carried out rapidly and the reaction mixture should be stirred only gently during the titration.
  - (b) In the subsequent samples, the full amount of alkali used in the first titration should be first added without stirring. The indicator should then be added and the titration completed to the desired endpoint by adding extra alkali.
2. The same amount of the indicator solution should be added while taking different readings.

*Observations and calculations*

Volume of water sample taken for each titration = 100 ml

Concordant volume of N/50  $\text{Na}_2\text{CO}_3$  used = A ml

$$N_1 V_1 = N_2 V_2$$

$$(\text{CO}_2) (\text{Na}_2\text{CO}_3)$$

$$N_1 \times 100 = \frac{1}{50} \times A$$

$$\text{Therefore (Normality of the sample w.r.t CO}_2) = \frac{A}{50 \times 100}$$

$$\text{Strength} = \frac{A \times 22}{50 \times 100} \text{ g/l}$$



$$\begin{aligned}\text{or Free CO}_2 &= \frac{A \times 22 \times 1000}{50 \times 100} \text{ mg/l} \\ &= 4.4 \times A \text{ mg/l}\end{aligned}$$

### 3.1.2 Determination of Acidity of a water sample

#### Significance

Measurement of acidity is important as acidic waters are corrosive, and corrosion-producing substances have to be controlled or removed. In the lime-soda process of water softening, amounts of reagents to be added have to be adjusted to account for the acidity of the sample. In the phosphate conditioning of boiler-feed water, the pH has to be adjusted to about 9.5; the choice of a suitable phosphate therefore depends on the measurement of acidity of the sample. Measurement of methyl orange acidity is important in calculating the quantities of chemicals required to neutralise the mineral acidity of the industrial wastes before they can be discharged into receiving waters (rivers, streams or lakes).

#### Reagents Required

1. Standard sodium hydroxide solution (N/50)
2. Methyl orange indicator solution
3. Phenolphthalein indicator solution
4. Sodium thiosulphate solution (N/10)

#### Theory

The acidity of a sample may be determined by titrating it against a standard alkali solution upto the stoichiometric equivalence point. The accurate identification of the stoichiometric equivalence point being very difficult, the titration is carried to an arbitrary end-point pH. The acidity, therefore, becomes a measure of the amount of a base required to neutralise a given sample to a specific pH:



For mineral acids, the titration is carried to a pH of about 4.5 by using methyl orange indicator, giving a colour change from red to yellow. The acidity thus determined is called Methyl Orange Acidity. Total Acidity or Phenolphthalein Acidity is determined by carrying the titration to phenolphthalein end-point of pH 8.3 (thus measuring mineral acids, organic acids and free  $\text{CO}_2$ ) indicated by appearance of pink colour. The results are expressed as parts of equivalent  $\text{CaCO}_3$  per million parts of water.

#### Procedure

(a) *Methyl Orange Acidity*: Pipet out 100 ml of the sample and discharge it near the bottom of a titration flask. Add 1 drop of N/10  $\text{Na}_2\text{S}_2\text{O}_3$  solution to destroy any residual chlorine. Add 2 drops of methyl orange indicator and



titrate with N/50 NaOH solution until the red colour changes to yellow. Take a number of readings and record the concordant volume as A ml.

(B) *Phenolphthalein Acidity*: Proceed as above using 2 drops of phenolphthalein (in place of methyl orange) indicator and titrate the sample until the pink colour persists for at least 30 seconds. Take a number of readings and record the concordant volume as B ml.

#### Precaution

- (1) To avoid loss of  $\text{CO}_2$ , the titration should be carried out quickly and vigorous shaking should be avoided.

#### Observations and Calculations

Volume of water sample taken for each titration = 100 ml

Volume of N/50 NaOH used in presence of methyl orange indicator = A ml

Volume of N/50 NaOH used in presence of phenolphthalein indicator = B ml

#### (A) Methyl Orange Acidity

$$\begin{array}{ccc} N_1 V_1 & = & N_2 V_2 \\ \text{(Sample)} & & \text{(N/50 NaOH)} \end{array}$$

$$N_1 \times 100 = \frac{1}{50} \times A$$

$$\text{or } N_1 = \frac{A}{50 \times 100}$$

$$\begin{aligned} \text{Methyl Orange Acidity (as CaCO}_3\text{)} &= \frac{A \times 50}{50 \times 100} \text{ g/l} \\ &= \frac{A \times 50 \times 1000}{50 \times 100} \text{ ppm} \\ &= A \times 10 \text{ ppm} \end{aligned}$$

$$\begin{aligned} \text{(B) Phenolphthalein Acidity} &= \frac{B \times 50 \times 1000}{50 \times 100} \text{ ppm} \\ &= B \times 10 \text{ ppm} \end{aligned}$$

### 3.1.3 Determination of Alkalinity of a water sample

#### Significance

Highly alkaline waters being usually unpalatable, upper limits with respect to phenolphthalein alkalinity and total alkalinity have been specified for municipal water supplies. Alkaline waters when used in boilers for steam



generation may lead to precipitation of sludges, deposition of scales and cause caustic embrittlement. A knowledge of the kinds of alkalinity present in water and their magnitudes is important

1. In calculating the amounts of lime and soda needed for water-softening,
2. In maintaining a pH range where acids produced by hydrolysis of salts (like  $\text{MgCl}_2$ ,  $\text{FeCl}_2$ ) and coagulants [ $\text{Al}_2(\text{SO}_4)_3$  and  $\text{Fe}_2(\text{SO}_4)_3$ ] may be effectively neutralised,
3. In corrosion control, and
4. In internal conditioning of boiler-feed water.



Caustic alkalinity of industrial wastes has to be neutralised before discharging them into rivers or other receiving waters. Waters containing alkalinity in excess of alkaline earth concentrations are not suitable for irrigation purposes.

#### Reagents Required

1. Standard sulphuric acid solution (N/50)
2. Phenolphthalein indicator solution
3. Methyl orange indicator solution.


#### Theory

The alkalinity of a water sample may be determined volumetrically by titrating it with a standard acid to an arbitrary pH using an indicator. When the pH of the sample is above 8.3, titration is first carried out using phenolphthalein indicator. At the end point, when the indicator changes from pink to colourless, the pH is lowered to about 8.3. The volume of the acid (A ml) used upto this point corresponds to the complete neutralisation of hydroxide and conversion of all the carbonate into bicarbonate:



A ml.

The alkalinity measured upto this point is called Phenolphthalein Alkalinity. Beyond the phenolphthalein end-point, titration is continued using methyl orange indicator. The colour change from yellow to red occurs at a pH of about 4.5 and the additional volume of acid (B ml) used corresponds to the complete neutralisation of all the bicarbonate whether present originally or obtained from  $\text{CO}_3^{2-}$  (Reaction 3.14):




B ml.

The total volume of acid [(A+B) ml] used in the two titrations, therefore, corresponds to the neutralisation of hydroxide, carbonate and bicarbonate and is, thus, a measure of Total Alkalinity, also called Methyl Orange Alkalinity. Alkalinity is expressed as parts of equivalent  $\text{CaCO}_3$  per million parts of water.

From the measurements for Phenolphthalein Alkalinity and Methyl Orange Alkalinity, it is possible to calculate the magnitudes of various forms of alkalinity, namely, Hydroxide Alkalinity, Carbonate Alkalinity and Bicarbonate



Alkalinity. If it is assumed (with only negligible error) that hydroxide and bicarbonate cannot co-exist, as they react to give carbonate:



we are left with the following five possible situations:

- (1) Hydroxide only
- (2) Carbonate only
- (3) Hydroxide and Carbonate
- (4) Carbonate and Bicarbonate
- (5) Bicarbonate only


(1) When the sample contains *only Hydroxide*, the neutralisation is complete at the phenolphthalein end-point (Reaction 3.13) and so *B*, the additional volume of acid needed for neutralisation to methyl orange end-point, will be zero. In this case, Hydroxide Alkalinity is equal to Phenolphthalein Alkalinity, which is also the Total Alkalinity.

(2) For samples containing *only Carbonate*, titration to phenolphthalein end-point corresponds to the complete conversion of carbonate to bicarbonate or what is also known as half-neutralisation of carbonate (Reaction 3.14). This means that exactly the same amount of additional acid will be required for further titration to methyl orange end-point (Reaction 3.15).

(3) For samples containing *Hydroxide and Carbonate*, titration to phenolphthalein end-point corresponds to complete neutralisation of hydroxide and half neutralisation of carbonate (Reactions 3.13 and 3.14), whereas titration from phenolphthalein end-point to methyl orange end-point corresponds to neutralisation of bicarbonate (Reaction 3.15) obtained from carbonate in reaction 3.14

Hence in this case,  $A > B$ . Also, the acid required to neutralise the hydroxide (Reaction 3.13) is  $(A - B)$  ml and that required for the complete neutralisation of carbonate (Reactions 3.14 and 3.15) is  $2B$  ml.

(4) For samples containing *Carbonate and Bicarbonate*, the titration to phenolphthalein end-point ( $A$  ml) corresponds to half-neutralisation of carbonate, i.e., conversion of carbonate to bicarbonate (Reaction 3.14) and the titration from phenolphthalein end-point to methyl orange end-point ( $B$  ml) represents half neutralisation of carbonate [i.e. the neutralisation of bicarbonate obtained from carbonate, which requires another  $A$  ml of the acid] and neutralisation of bicarbonate originally present in the sample.



For such a mixture, evidently,  $B > A$ . Carbonate Alkalinity is equivalent to  $2A$  ml of the acid and Bicarbonate Alkalinity is equivalent to  $(B - A)$  ml of the acid.

(5) When the sample contains *Only Bicarbonate*, it does not give a pink



colour with phenolphthalein indicator. Therefore A, the volume of acid consumed with phenolphthalein indicator is zero. Titration to methyl orange end-point represents the complete neutralisation of bicarbonate (Reaction 3.15). Bicarbonate Alkalinity is therefore equal to Total or Methyl Orange Alkalinity.

### Procedure

With a pipet, transfer 100 ml of the water sample into a titration flask. Add 2 drops of phenolphthalein indicator and titrate against  $N/50$   $H_2SO_4$  until the pink colour just disappears. Record the volume of acid consumed as A ml. To the same solution add 2-3 drops of methyl orange indicator and titrate further until the colour changes from yellow to red. Record the additional volume of acid consumed as B ml. Repeat the whole process a number of times to get concordant readings.

### Observations and Calculations

Volume of sample taken for each titration = 100 ml  
 Volume of  $N/50$   $H_2SO_4$  used to phenolphthalein end-point = A ml  
 Additional volume of  $N/50$  acid used to methyl orange end-point = B ml

$$\begin{array}{cc} N_1 V_1 & N_2 V_2 \\ \text{(sample)} & \text{(N/50 acid)} \end{array}$$

$$N_1 \times 100 = \frac{1}{50} \times A$$

$$\text{or } N_1 = \frac{1}{50} \times A \times \frac{1}{100}$$

$$\text{Strength (in terms of } CaCO_3) = \frac{1}{50} \times A \times \frac{1}{100} \times 50 \text{ g/l}$$

$$\begin{aligned} \text{or Phenolphthalein Alkalinity} &= \frac{1}{50} \times A \times \frac{1}{100} \times 50 \times 1000 \text{ mg/l} \\ &= 10 \times A \text{ ppm} \end{aligned}$$

$$\begin{aligned} \text{Similarly, Total Alkalinity or} \\ \text{Methyl Orange Alkalinity} &= \frac{1}{50} \times (A+B) \times \frac{1}{100} \times 50 \times 1000 \text{ mg/l} \\ &= 10 \times (A+B) \text{ ppm} \end{aligned}$$

$$\begin{aligned} \text{Hydroxide Alkalinity} &= \frac{1}{50} \times (A-B) \times \frac{1}{100} \times 50 \times 1000 \text{ mg/l} \\ &= 10 \times (A-B) \text{ ppm} \end{aligned}$$

$$\begin{aligned} \text{Hydroxide Ion concentration} &= \frac{1}{50} \times (A-B) \times \frac{1}{100} \times 17 \times 1000 \text{ mg/l} \\ &= 10 \times (A-B) \times 0.34 \text{ ppm} \\ &= \text{Hydroxide Alkalinity} \times 0.34 \text{ ppm} \end{aligned}$$



$$\begin{aligned}
 \text{Carbonate Alkalinity} &= \frac{1}{50} \times 2B \times \frac{1}{100} \times 50 \times 1000 \\
 &= 10 \times 2B \text{ ppm when } A > B \\
 \text{and} &= \frac{1}{50} \times 2A \times \frac{1}{100} \times 50 \times 100 \\
 &= 10 \times 2A \text{ ppm when } A \leq B \\
 \text{Carbonate Ion concentration} &= 10 \times 2B \times \frac{30}{50} \\
 &= 6 \times 2B \text{ ppm when } A > B \\
 \text{and} &= 6 \times 2A \text{ ppm when } A \leq B. \\
 \text{Bicarbonate Alkalinity} &= \frac{1}{50} \times (B-A) \times \frac{1}{100} \times 50 \times 1000 \\
 &= 10 \times (B-A) \text{ ppm} \\
 \text{Bicarbonate Ion concentration} &= 10 \times (B-A) \times \frac{61}{50} \text{ ppm} \\
 &= \text{Bicarbonate Alkalinity} \times 1.22 \text{ ppm}
 \end{aligned}$$

### Exercises

38. Write the structural formula of methyl orange. In what forms does it exist in acidic and alkaline medium?
39. Write the structural forms of methyl red indicator in alkaline and acidic medium.
40. Explain the action of phenolphthalein as an acid-base indicator.
41. In the determination of free  $\text{CO}_2$ , (a) Why is it preferable to use a standard solution of  $\text{Na}_2\text{CO}_3$  instead of  $\text{NaOH}$ ? (b) If  $\text{NaOH}$  solution is used, how will the results be affected if it is not free from  $\text{Na}_2\text{CO}_3$ ?
42. In the presence of heavy metal salts, what modification would you suggest to complete the titration rapidly?
43. What is the source of mineral acidity in water?
44. In acidity and alkalinity measurements, the titrant used ( $\text{Na}_2\text{CO}_3$  or  $\text{H}_2\text{SO}_4$ ) is usually N/50. Why?

### 3.2 Chloride Content

Chlorides usually occur as  $\text{NaCl}$ ,  $\text{CaCl}_2$ , and  $\text{MgCl}_2$ , and in widely varying concentrations, in all natural waters. They enter waters

- (a) by solvent action of water on salts present in soil,
- (b) from polluting materials like sewage (containing the salt used in household) and trade wastes (containing chloride used in manufacturing), and
- (c) In areas around sea from (i) salt-water droplets carried inland, by



wind, as spray from the sea, (ii) invasion (upstream flow) by sea waters into rivers that drain into sea.

### Significance

When present at concentrations above 250 ppm, chlorides impart an unacceptable taste to waters although no adverse affects have been observed on human beings regularly consuming waters with much higher concentrations of chlorides. Exceptionally high concentration of chloride in a water (as compared to that in other waters in the general vicinity and known to be unpolluted) may be considered as an indication of contamination by domestic waste water. Chloride ion concentration should be known

- (i) for deciding the type of desalting apparatus when brackish waters have to be used
- (ii) for treating industrial wastes before discharging them into natural bodies of water
- (iii) for controlling pumping of ground water from sea coasts where invasion by sea water can take place, and
- (iv) for applying correction factor in COD determination (where chloride interferes)


### 3.2.1 Determination of Chloride Content of a water sample by Mohr's Method (Argentometric)

#### Reagents Required


1. Standard silver nitrate solution (N/50)
2. Potassium chromate indicator solution ( $K_2CrO_4$ )
3. Solid  $CaCO_3$ .

#### Theory


Chloride ions in a neutral or faintly alkaline solution can be estimated by titration with a standard solution of  $AgNO_3$  using  $K_2CrO_4$  as indicator. The pH must be in the range of 7 to 8 because  $Ag^+$  ion is precipitated as  $AgOH$  at higher pH



and  $CrO_4^{2-}$  is converted to  $Cr_2O_7^{2-}$  at lower pH





$HCrO_4^-$  being a weak acid,  $CrO_4^{2-}$  ion concentration is decreased necessitating higher concentration of  $Ag^+$  for the solubility product of  $Ag_2CrO_4$  to be exceeded, thus leading to higher results. The required pH range can be achieved easily by adding a pinch of pure  $CaCO_3$  to the pink or red-coloured solution obtained at the end-point of the Methyl Orange Alkalinity determination (experiment 3.1.3):




Excess  $CaCO_3$ , being insoluble, does not interfere.



As  $\text{AgNO}_3$  solution is added from the burette to the chloride ion sample containing  $\text{CrO}_4^{2-}$ ;  $\text{Ag}^+$  reacts with both  $\text{Cl}^-$  and  $\text{CrO}_4^{2-}$  forming the respective precipitates:



But the red colour formed by the addition of each drop of  $\text{AgNO}_3$  disappears because of the large concentration of  $\text{Cl}^-$  ions in the solution:



As the concentration of  $\text{Cl}^-$  ions decreases, the red colour disappears more slowly and when all the chloride has been precipitated, a faint reddish or pinkish tinge persists in the white precipitate even after brisk shaking.

### Procedure

Add a pinch of pure  $\text{CaCO}_3$  to the solution obtained at the end of Methyl Orange Alkalinity determination, so that the red or pink colour vanishes. Add 1-1.5 ml of  $\text{K}_2\text{CrO}_4$  indicator solution and titrate against N/50  $\text{AgNO}_3$  taken in the burette until a permanent pink tinge persists in the white precipitate. Repeat the whole process a number of times to get concordant readings. Record the concordant volume as A ml.

### Precautions

- (1) The whole apparatus must be washed with distilled water.
- (2) The same amount of the indicator must be added each time.
- (3) The reaction mixture should be briskly shaken during the titration.

### Observations and Calculations

Volum of the sample taken each time = 100 ml

Concordant volume of N/50  $\text{AgNO}_3$  used = A ml

$$N_1 V_1 = N_2 V_2$$

( $\text{Cl}^-$  ion sample) ( $\text{AgNO}_3$ )

$$N_1 \times 100 = \frac{1}{50} \times A$$

Therefore

$$N_1 = \frac{1}{50} \times A \times \frac{1}{100}$$

Strength of  $\text{Cl}^-$  ions

$$= \frac{1}{50} \times A \times \frac{1}{100} \times 35.5 \text{ g/l}$$

$$= \frac{1}{50} \times A \times \frac{1}{100} \times 35.5 \times 1000 \text{ mg/l}$$

$$= 7.1 \times A \text{ ppm}$$




**Exercises**

45. How is the pH adjusted when the alkalinity is not being measured?
46. How does the presence of  $\text{NH}_4^+$  ions in the sample affect the determination?
47. What is meant by indicator-blank correction? How can it be avoided in the chloride ion estimation?
48. What is the effect of temperature on the determination?
49. How is the test performed on waters having (i) colour and turbidity, and (ii)  $\text{H}_2\text{S}$  odour?

**3.3 Hardness**

Water samples that do not readily produce lather with soap, or deposit scale on the walls of the container when there is appreciable change in temperature, are called Hard Waters. Principal hardness-causing cations are  $\text{Ca}^{2+}$  and  $\text{Mg}^{2+}$ . Other divalent metallic cations that cause hardness are  $\text{Fe}^{2+}$ ,  $\text{Mn}^{2+}$  and  $\text{Sr}^{2+}$  but these are usually present in small amounts. The cations react with soaps (sodium or potassium salts of fatty acids) to form precipitates:



Lather is produced only after sufficient soap has been added to precipitate all the hardness causing ions.

At higher concentrations, these ions associate themselves with certain anions ( $\text{CO}_3^{2-}$ ,  $\text{SO}_4^{2-}$ ,  $\text{Cl}^-$ ,  $\text{NO}_3^-$ ,  $\text{SiO}_3^{2-}$ , etc.) and produce scale.

$\text{Al}^{3+}$  and  $\text{Fe}^{3+}$  may also contribute to the hardness of water but their ionic concentrations in natural waters are generally negligible. Surface waters contain very small amounts of dissolved impurity. However, rain water percolates into soil, it dissolves  $\text{CO}_2$  (released by bacterial action on organic matter) and attacks basic materials like limestone formations, dolomite, etc., and dissolves the insoluble carbonates present:



Sulphates, chlorides, silicates, etc., of Ca, Mg, Na, K, Al, etc., present as impurities in the limestone become exposed to the solvent action of water and pass into solution, thereby adding to the hardness of water.

Hardness is generally reported in terms of calcium carbonate equivalent and is calculated by the general formula:

$$\text{Hardness (in mg/l) as CaCO}_3 = \text{M}^{2+} \text{ (in mg/l)} \times \frac{50}{\text{eq. wt. of M}^{2+}} \quad (3.25)$$

[50 being the eq. wt. of  $\text{CaCO}_3$ ]

where  $\text{M}^{2+}$  is any divalent metallic ion.



*Units of Hardness*

1. Parts per million (ppm) is the most commonly used unit of hardness and represents the number of parts of calcium carbonate, equivalent to hardness causing ions present, per million parts of water.

$$\begin{aligned}
 1 \text{ ppm} &= 1 \text{ part CaCO}_3 \text{ equivalent hardness in } 10^6 \text{ parts of water} \\
 &= 1 \text{ g CaCO}_3 \text{ equivalent hardness in } 10^6 \text{ g water} \\
 &= 1 \text{ mg CaCO}_3 \text{ equivalent hardness in } 10^6 \text{ mg or } 10^3 \text{ g water} \\
 &= 1 \text{ mg CaCO}_3 \text{ equivalent hardness in 1 litre of water.}
 \end{aligned}$$

2. Degree Clark ( $^{\circ}\text{Cl}$ ) is the number of grains ( $1 \text{ grain} = \frac{1}{7000} \text{ lb}$ ) of  $\text{CaCO}_3$  equivalent to hardness causing ions in one gallon (10 lbs) of water.

$$\begin{aligned}
 \text{Thus } 1^{\circ}\text{Cl} &= \frac{1}{7000} \text{ parts of CaCO}_3 \text{ equivalent hardness in 10 parts of water} \\
 &= \frac{1}{70000} \text{ parts of CaCO}_3 \text{ equivalent hardness in 1 part of water} \\
 &= \frac{10^6}{70000} \text{ parts of CaCO}_3 \text{ equivalent hardness in } 10^6 \text{ parts of water} \\
 &= \frac{100}{7} \approx 14.3 \text{ ppm}
 \end{aligned}$$

3. Degree French ( $^{\circ}\text{F}$ ) is the number of parts of  $\text{CaCO}_3$  equivalent to hardness causing ions in  $10^5$  parts of water.

$$\begin{aligned}
 \text{Thus } 1^{\circ}\text{F} &= 1 \text{ part CaCO}_3 \text{ equivalent hardness in } 10^5 \text{ parts of water} \\
 &= \frac{10^6}{10^5} \text{ parts CaCO}_3 \text{ equivalent hardness in } 10^6 \text{ parts of water} \\
 &= 10 \text{ ppm}
 \end{aligned}$$

Relationship between various units:  $1^{\circ}\text{F} = 10 \text{ ppm} = 0.7^{\circ}\text{Cl}$

Water is generally called—

Soft, when the degree of hardness is  $< 75 \text{ ppm}$



Moderately hard, when the degree of hardness is between 75-150 ppm

Hard, when the degree of hardness is between 150-300 ppm

Very hard, when the degree of hardness is  $> 300 \text{ ppm}$ .

*Types of Hardness*

The portion of the total hardness that can be largely removed by boiling is known as Temporary Hardness. Boiling converts the bicarbonates present into insoluble carbonates and hydroxides, which can be removed by filtration.





The portion of the hardness that cannot be removed by boiling is termed as Permanent Hardness.

In order to relate the hardness to the chemical species, it is customary to refer the part of the total hardness that is chemically equivalent to the bicarbonate plus carbonate alkalinities as Carbonate Hardness (CH) and the amount of hardness which is in excess of CH as Non-Carbonate Hardness (NCH).

With respect to the metallic ion present, hardness is classified into Calcium Hardness and Magnesium Hardness (other cations being neglected as their contribution to hardness is not appreciable).

### 3.3.1 Outline of Various Methods

(1) Hardness is best calculated from a complete mineral analysis of water.

$$\begin{aligned} \text{Total hardness in ppm} = & 2.5 \times \text{mg/l of Ca}^{2+} + 4.12 \times \text{mg/l of Mg}^{2+} + \\ & (1.79 \times \text{mg/l of Fe}^{2+} + 1.82 \times \text{mg/l of Mn}^{2+} + \\ & 1.14 \times \text{mg/l of Sr}^{2+}). \end{aligned} \quad (3.28)$$

$$[\text{Fe} = 55.85, \text{Ca} = 40, \text{Mg} = 24.3, \text{Mn} = 54.9, \text{Sr} = 87.6]$$

The last three make only an insignificant contribution to total hardness.

The method is applicable to all waters and gives results of high accuracy. However, such a detailed analysis is not done in routine work and other methods have to be used.

As both alkalinity and hardness are expressed in terms of  $\text{CaCO}_3$ , CH and NCH may be calculated as follows:



$$\begin{aligned} \text{When alkalinity} & < \text{total hardness} \\ \text{CH (in ppm)} & = \text{Alkalinity (in ppm)} \end{aligned} \quad (3.29)$$

$$\begin{aligned} \text{When alkalinity} & \geq \text{total hardness} \\ \text{CH (in ppm)} & = \text{Total hardness (in ppm)} \end{aligned} \quad (3.30)$$

$$\text{NCH} = \text{Total hardness} - \text{CH.}$$

(2) *Hehner's Method.* Boiling removes Temporary Hardness by converting bicarbonates into insoluble carbonates and hydroxides [reactions 3.26 and 3.27] which are removed by filtration, thereby causing an equivalent decrease in alkalinity. Measurement of alkalinity before and after boiling thus affords a method of determination of temporary hardness.



(3) *Determination of Permanent Hardness using a mixture of  $\text{Na}_2\text{CO}_3$  and  $\text{NaOH}$ .* An aliquot of the hard water sample is boiled with a known excess of alkali mixture ( $\text{Na}_2\text{CO}_3 + \text{NaOH}$ ). This precipitates permanent hardness due to  $\text{Ca}^{2+}$  and  $\text{Mg}^{2+}$ :



The excess of the unused alkali is back-titrated with a standard acid using



methyl orange indicator. The permanent hardness of the sample can be calculated from the amount of the alkali mixture consumed.  $\text{Ca}(\text{HCO}_3)_2$  and  $\text{Mg}(\text{HCO}_3)_2$  present in the sample do not consume any alkali as an equivalent amount of  $\text{Na}_2\text{CO}_3$  is produced.



It is customary, however, to remove temporary hardness by boiling before the addition of alkali mixture.

#### (4) *Determination of Magnesium Hardness using NaOH/lime water*

The carbonate hardness (CH) of the hard water sample is converted into non-carbonate hardness (NCH) by neutralising a definite volume of the sample with HCl to methyl orange end-point, or best the solution at the end-point of methyl orange alkalinity determination experiment is taken and heated to boil off  $\text{CO}_2$ . A known excess of NaOH (Lime water is preferred as NaOH may contain  $\text{Na}_2\text{CO}_3$  as impurity) is added and the reaction mixture is boiled gently for 10-15 minutes. Magnesium hardness is precipitated as  $\text{Mg}(\text{OH})_2$  :



The precipitate is filtered and the excess of NaOH (or lime) left unconsumed is determined by titrating the filtrate against standard acid. The amount of NaOH (or lime) consumed is a measure of the magnesium hardness of the sample.

(5) *Soap Titration:* The fact that sufficient soap solution has to be added to precipitate all the hardness causing ions from a hard water sample before lather is formed is utilized in the determination of hardness. A suitable aliquot of the hard water sample is taken in a stoppered flask and after successive additions of a soap solution (previously standardised by titration against standard hard water) from a burette, the mixture is vigorously shaken. The stage where the lather formed persists for 2-3 minutes is taken as the end-point of the titration. The hardness of the water sample is equivalent to the volume of the soap solution used minus lather factor (Volume of soap solution used to produce lather with a volume of distilled water equal to the aliquot of the hard water sample).

### 3.3.2 *Determination of Hardness by EDTA*

#### *Significance of Hardness Determination*

Though hard waters are as palatable as soft waters, a knowledge of the magnitude and type of hardness is important in determining the suitability of a water for domestic and industrial purposes. Use of hard waters for cleansing purposes is unsatisfactory as they increase the consumption of soaps. This drawback has been partly overcome by the use of synthetic



detergents but for personal hygiene, soap is preferred and hard waters remain objectionable. Hard waters offer difficulties in dyeing of textiles, are uneconomical and even hazardous in steam generation and impart many of the undesirable characteristics to the finished products in paper industry, beverages, dairies, and allied industries. Soft waters are required for an innumerable number of other industries also.


In devising an efficient and economical softening process, determination of total hardness and the relative amounts of CH & NCH and calcium & magnesium hardness is important.

### Regents Required


1. Standard hard water ( $N/50$ ,  $1\text{ ml} \equiv 1\text{ mg CaCO}_3$ )
2. EDTA solution ( $N/50$ )
3. Ammonium chloride-ammonium hydroxide buffer ( $\text{pH} \sim 10$ ).
4. Eriochrome Black T indicator solution.

## Theory



The disodium salt of ethylenediamine tetraacetic acid (EDTA)



ionises in water to give  $2 \text{Na}^+$  ions and a strong chelating agent




which for simplicity can be represented by  $H_2Y^{2-}$ . It forms complexes with  $Ca^{2+}$  and  $Mg^{2+}$  and other divalent or higher valent cations represented by the reactions:




The dissociation of these complexes is governed by the pH of the solution and the complexes with hardness causing divalent ions are stable in alkaline medium (pH range 8-10).

The Indicator used is a complex organic compound [sodium-1-(1-hydroxy-2-naphthylazo) -6-nitro-2-naphthol-4- sulphate]:






commonly known as Eriochrome Black T. It has two ionisable phenolic hydrogen atoms and for simplicity is represented as  $\text{Na}^+\text{H}_2\text{In}^-$  :




In the pH range 7-11, the indicator reacts with the metal ion to form a weak complex with a wine red colour:




**Buffer Solution:** The optimum pH for the experiment is  $10.0 \pm 0.1$  and is adjusted by  $\text{NH}_4\text{OH} + \text{NH}_4\text{Cl}$  buffer.


When a small amount of the indicator solution is added to a hard water sample whose pH has been controlled by the addition of the buffer solution, the indicator reacts with  $\text{Mg}^{2+}$  to produce




wine red colour. As EDTA ( $\text{H}_2\text{Y}^{2-}$ ) is added, free  $\text{Ca}^{2+}$  ions are first complexed to  $\text{CaY}^{2-}$ , this being the most stable complex;



Free  $\text{Mg}^{2+}$  ions then react to give Mg-EDTA complex which is less



stable than Ca-EDTA complex but more stable than Mg-indicator complex. Therefore, if an extra drop of EDTA is added after all the free  $\text{Ca}^{2+}$  and  $\text{Mg}^{2+}$  ions have been complexed, EDTA takes up  $\text{Mg}^{2+}$  from the weak Mg-indicator complex to form stable Mg-EDTA complex simultaneously liberating the indicator in the free form



which makes the end-point of the titration.

### Procedure

#### (a) Standardisation of EDTA solution with Standard Hard Water

(1 ml S.H.W.  $\equiv$  1 mg  $\text{CaCO}_3$ )

Pipet out 10 ml of standard hard water into a conical flask. Add to it 40 ml distilled water with a measuring cylinder, 2 ml of buffer solution and 2 drops of Eriochrome black T indicator. A wine red colour appears. Titrate against EDTA solution, taken in the burette, to a colour change from wine red to pure blue. Record the volume of EDTA used as A ml. Take three concordant readings.



(b) *Determination of Total Hardness:* Pipet out 50 ml of the hard water sample into a conical flask, and 2 ml buffer solution and 2 drops of the indicator. Titrate against EDTA till the wine red colour changes to pure blue. Record the volume of EDTA used as B ml. This corresponds to the total hardness of the water sample.

(c) *Determination of Temporary and Permanent Hardness:* Take 250 ml of the hard water sample in a 500-ml beaker and boil gently for about one hour. Cool; filter into a 250-ml measuring flask and make the volume up to the mark. Take 50 ml of this solution and proceed in the same way as in (b) above. The volume of EDTA used (C ml) corresponds to permanent hardness of the water sample. Temporary hardness is calculated by subtracting permanent hardness from total hardness.

(d) *Determination of Calcium and Magnesium Hardness*


#### Method I

##### Reagents Required


1. Standard EDTA solution (N/50, 1 ml  $\equiv$  1 mg  $\text{CaCO}_3$ ) or standardise as in (a) above
2. Diethylamine
3. Calcon indicator solution.

##### Theory

$\text{Mg}^{2+}$  in the hard water sample is precipitated as  $\text{Mg}(\text{OH})_2$  by adding diethylamine which raises the pH of the solution to about 12.5.



$\text{Ca}^{2+}$  can then be titrated with EDTA using calcon indicator:



[Calcon, Solochrome Dark Blue or Eriochrome Blue Black R—Chemical name is Sodium 1-(2-hydroxy-1-naphthylazo)-2-naphthol-4-sulphonate]. The colour change at the end-point is from pink to pure blue.

##### Procedure

Pipet out 50 ml of the hard water sample into a conical flask. Add 3 ml of diethylamine and 4 drops of calcon indicator. Keep the flask on a magnetic stirrer and titrate against standard EDTA solution until the colour



changes from pink to pure blue. The volume of EDTA used [ $D_1$  ml] corresponds to calcium hardness. Magnesium hardness is obtained by subtracting calcium hardness from total hardness.


## Method II

### Reagents Required

1. Standardised EDTA solution
2. Calcium precipitating buffer solution
3. Ammonium chloride-ammonium hydroxide buffer (pH ~10)
4. Eriochrome Black T indicator solution.

### Theory

$\text{Ca}^{2+}$  in the hard water sample is precipitated as calcium oxalate by adding calcium precipitating buffer solution:



The precipitate is filtered and  $\text{Mg}^{2+}$  in the filtrate is titrated with standard EDTA using Eriochrome Black T indicator.

### Procedure

Measure out 200 ml of the hard water sample into a 500-ml dry beaker and add 40 ml of the calcium precipitating buffer solution while constantly stirring the mixture with a glass rod. Allow the precipitate to settle down for about 1 hour and filter through a dry funnel fitted with two pieces of Whatman filter paper No. 42 into a dry flask. Do not wait for the filtration to be completed. Measure 60 ml of the filtrate into a conical flask, add 50 ml of distilled water, 5ml  $\text{NH}_4\text{OH}/\text{NH}_4\text{Cl}$  buffer (pH ~ 10), 4 drops of Eriochrome black T indicator and titrate against standard EDTA solution. The volume of EDTA used ( $D_2$  ml) corresponds to magnesium hardness. Calcium hardness is obtained by subtracting magnesium hardness from the total hardness.

### Calculations

(a) Standardisation of EDTA solution:

1 ml S.H.W.	$\equiv 1 \text{ mg CaCO}_3$
A ml EDTA	$\equiv 10 \text{ ml S.H.W.}$
	$\equiv 10 \text{ mg CaCO}_3$
1 ml EDTA	$\equiv \frac{10}{A} \text{ mg CaCO}_3$



## 54. APPLIED CHEMISTRY

(b) Total Hardness:

50 ml hard water

$$\equiv B \text{ ml EDTA}$$

$$\equiv B \times \frac{10}{A} \text{ mg CaCO}_3$$

1 ml hard water

$$\equiv B \times \frac{10}{A \times 50} \text{ mg CaCO}_3$$

1000 ml hard water

$$\equiv B \times \frac{10}{A} \times \frac{1000}{50} \text{ CaCO}_3$$

$$= \frac{B}{A} \times 200 \text{ mg CaCO}_3$$

or Total hardness

$$= \frac{B}{A} \times 200 \text{ ppm}$$

(c) Permanent Hardness:

50 ml hard water

$$\equiv C \text{ ml EDTA}$$

$$\equiv C \times \frac{10}{A} \text{ mg CaCO}_3$$

1000 ml hard water

$$\equiv C \times \frac{10}{A} \times \frac{1000}{50} \text{ mg CaCO}_3$$

$$\equiv \frac{C}{A} \times 200 \text{ mg CaCO}_3$$

or Permanent hardness

$$= \frac{C}{A} \times 200 \text{ ppm}$$

Temporary hardness

$$= \text{Total hardness} - \text{Permanent hardness}$$

$$= \left[ \frac{B}{A} \times 200 - \frac{C}{A} \times 200 \right] \text{ ppm}$$

(d) Method I-Calcium Hardness

50 ml hard water

$$\equiv D_1 \text{ ml EDTA}$$

$$\equiv D_1 \times \frac{10}{A} \text{ mg CaCO}_3$$

1000 ml hard water

$$\equiv D_1 \times \frac{10}{A} \times \frac{1000}{50} \text{ mg CaCO}_3$$

$$= \frac{D_1}{A} \times 200 \text{ mg CaCO}_3$$

Therefore, Calcium hardness

$$= \frac{D_1}{A} \times 200 \text{ ppm}$$

Magnesium hardness

$$= \left[ \frac{B}{A} \times 200 - \frac{D_1}{A} \times 200 \right] \text{ ppm}$$



## Method II - Magnesium hardness

$$240 \text{ ml filtrate} \equiv 200 \text{ ml hard water}$$

$$1 \text{ ml filtrate} \equiv \frac{200}{240} \text{ ml hard water}$$

$$60 \text{ ml filtrate} \equiv \frac{200 \times 60}{240} \text{ ml hard water}$$

$$= 50 \text{ ml hard water}$$

Therefore, hardness of 60 ml of filtrate is equal to the magnesium hardness of 50 ml of hard water sample.

$$50 \text{ ml hard water} \equiv D_2 \text{ ml EDTA}$$

$$\equiv D_2 \times \frac{10}{A} \text{ mg CaCO}_3$$

$$1000 \text{ ml hard water} \equiv D_2 \times \frac{10}{A} \times \frac{1000}{50} \text{ mg CaCO}_3$$

$$\text{or Magnesium hardness} = \frac{D_2}{A} \times 200 \text{ ppm}$$

$$\text{Calcium hardness} = \left[ \frac{B}{A} \times 200 - \frac{D_2}{A} \times 200 \right] \text{ ppm}$$

## Exercises

50. Which is the best method of hardness determination and why?
51. What is the effect on the end-point with Eriochrome black-T indicator if the hard water sample does not contain  $\text{Mg}^{2+}$ ?
52. To obtain a sharp end-point with Eriochrome black-T indicator, how can  $\text{Mg}^{2+}$  ions be added without introducing any error?
53. Why and how is the pH value adjusted to about 10?
54. Describe and calculate the hardness of water samples giving the following analysis:

(a)	Impurity	Amount in mg/l or ppm	Impurity	Amount in mg/l or ppm
	$\text{Ca}^{2+}$	20	$\text{SO}_4^{2-}$	96
	$\text{K}^+$	39	$\text{HCO}_3^-$	183
	$\text{Na}^+$	23	$\text{Cl}^-$	35.5
	$\text{Mg}^{2+}$	48.6		
(b)	$\text{Mg}^{2+}$	24.3	$\text{Cl}^-$	35.5
	$\text{Na}^+$	23	$\text{SO}_4^{2-}$	48
	$\text{Ca}^{2+}$	40	$\text{HCO}_3^-$	305
	$\text{K}^+$	78		



55. 100 ml of a water sample required 10 ml of N/50 HCl for neutralisation to methyl orange end-point. Another 100 ml of the same sample, after being boiled and filtered, required 0.2 ml of N/50 HCl for complete neutralisation. Calculate temporary hardness of water sample (Hehner's method).
56. 100 ml of a hard water sample were taken in a 250-ml beaker and boiled to precipitate temporary hardness. 20 ml of an alkali mixture solution ( $\text{NaOH} + \text{Na}_2\text{CO}_3$ ), whose 10 ml required 8 ml of N/10 HCl for neutralisation to methyl orange end-point, were then added. The reaction mixture was heated to boiling, cooled and filtered. The filtrate required 13 ml of N/10 HCl for complete neutralisation. Calculate permanent hardness of the water sample.
57. 100 ml of a hard water sample were neutralised with HCl using methyl orange indicator. The solution was then boiled with 25 ml of N/50 NaOH and filtered. The filtrate required 21 ml of N/50 HCl for complete neutralisation. Calculate magnesium hardness of the water sample.
58. 70 ml of a standard hard water (containing 0.28 g  $\text{CaCO}_3$ /litre) required 20.1 ml of a given soap solution for producing lather that persisted for 5 minutes. 70 ml of tap water under the same conditions required 14.5 ml of soap solution. 70 ml of the same water sample, after being boiled, filtered and diluted with distilled water to original volume, required 5.4 ml of the soap solution. If 70 ml of distilled water requires 0.5 ml of the same soap solution for producing lather, calculate total, permanent and temporary hardness of tap water in degrees Clark. Also report the result in degrees French and in ppm.

### 3.4 Dissolved Oxygen (D.O.) and Oxygen Demand

Oxygen is poorly soluble in water. Since it does not react with water chemically, its amount present in water at saturation at any given temperature and pressure can be calculated by Henry's law. Under a pressure of one atmosphere, the solubility of oxygen of air in distilled or fresh waters with low solid concentrations varies from 14.5 mg/l at  $0^\circ\text{C}$  to about 7.5 mg/l at  $30^\circ\text{C}$ . The solubility is less in saline waters and at a given temperature decreases with increase in the concentration of the impurities.

#### 3.4.1 Determination of Oxygen dissolved in a water sample

##### *Significance of the Test*

In steam generation, D.O. is one of the important factors causing corrosion of the boiler material. From boiler-feed water, D.O. is removed by physical and chemicals means. Measurement of D.O. is necessary to control these processes.

If sufficient D.O. is not present in polluted water, nuisance conditions are developed due to anaerobic degradation of the pollutants. D.O. test is thus vital as a means of controlling the rate of aeration to ensure aerobic



conditions and also to prevent excessive use of air. The test also helps in maintaining dissolved oxygen levels that will support the desired aquatic life (fish, etc.).




### Reagents Required

1. Standard sodium thiosulphate solution (N/40)
2. Potassium permanganate solution (N/10)
3. Potassium oxalate solution (2%)
4. Manganous sulphate solution (48%)
5. Alkaline potassium iodide solution
6. Freshly prepared starch solution
7. Concentrated sulphuric acid.


### Theory

The iodometric (Winkler) method is based on the fact that in alkaline medium D.O. oxidises  $\text{Mn}^{2+}$  to  $\text{Mn}^{4+}$ , which in acidic medium oxidises  $\text{I}^-$  to free iodine. The amount of iodine released, which can be titrated with a standard solution of sodium thiosulphate, is thus equivalent to the D.O. originally present.

In the modified Winkler method, the interference due to certain oxidising agents such as  $\text{NO}_2^-$  or reducing agents such as  $\text{Fe}^{2+}$  or  $\text{SO}_3^{2-}$  is removed by treating the sample with an excess of  $\text{KMnO}_4$  in acid medium. The following reactions take place :




$\text{NO}_3^-$  and  $\text{SO}_4^{2-}$  formed in reactions (3.46) and (3.47) do not interfere.  $\text{Fe}^{3+}$  interferes only when present in amounts above 10 mg/l. This interference is avoided by converting  $\text{Fe}^{3+}$  into poorly dissociated complex  $\text{FeF}_6^{3-}$  by adding KF :






Excess of  $\text{KMnO}_4$  is destroyed by adding potassium oxalate :



$\text{MnSO}_4$  and alkaline  $\text{KI}$  are then added when a white precipitate of  $\text{Mn}(\text{OH})_2$  is formed.




The oxygen dissolved in the sample oxidises some of the  $\text{Mn}^{2+}$  to  $\text{Mn}^{4+}$  which is precipitated as brown hydrated manganese dioxide :



(This process is sometimes called fixation of oxygen).

On acidifying the solution, manganese in the higher oxidation state oxidises  $\text{I}^-$  to free iodine :



The iodine liberated is titrated with standard  $\text{Na}_2\text{S}_2\text{O}_3$  solution using freshly prepared starch solution as indicator:



### Procedure

Collect the water sample in a 300-ml glass-stoppered (water tight) bottle. With the help of a graduated pipet, add 0.7 ml conc.  $\text{H}_2\text{SO}_4$  and 0.2 ml. (4 drops)  $\text{KMnO}_4$  solution. Stopper the bottle and mix the contents of the bottle by inverting it a few times. If the permanganate colour disappears within 5 minutes, add additional amount of  $\text{KMnO}_4$ . Add 0.5 ml of potassium oxalate solution, stopper and mix well. Add additional amounts of oxalate solution if the permanganate colour is not discharged within 10 minutes. Add 2 ml of  $\text{MnSO}_4$  solution followed by 3 ml of alkaline  $\text{KI}$  solution. Stopper and mix by rotating and inverting the bottle 10 to 15 times and allow to stand. After about 2 minutes, shake and allow the precipitate to settle. When some portion of the liquid below the stopper is clear, add 1 ml




conc.  $\text{H}_2\text{SO}_4$ . Stopper and mix until the precipitate is completely dissolved. Take 204.4 ml (with a measuring cylinder) of this solution in a titration flask and titrate slowly against (N/40)  $\text{Na}_2\text{S}_2\text{O}_3$  solution. When the colour of the solution is very light yellow, add about 2 ml of freshly prepared starch solution and continue the titration to the first disappearance of the blue colour. Repeat the whole experiment two to three times and record the mean volume of  $\text{Na}_2\text{S}_2\text{O}_3$  used as A ml.

#### Precautions

- (1) As far as possible, the sample should not be allowed to come in contact with air.

In most cases of interest, the D.O. level of the sample is below saturation, and exposure to air will lead to higher results. For reducing the contact of the sample with air—

- (a) the sample should be collected from the tap using a rubber tubing whose other end should be lowered to the bottom of the bottle. Water should be allowed to overflow for sometime.
  - (b) the stopper of the bottle should be removed only when some reagent is to be added.
  - (c) while replacing the stopper, care should be taken to exclude air bubbles.
- (2) While adding various reagents, the tip of the graduated pipet should be dipped below the surface of the liquid.
  - (3) The flocculated material formed on addition of alkaline KI should be moved throughout the solution to enable all the oxygen to react. The reaction [which may also be represented as stoichiometric absorption of dissolved molecular oxygen by  $\text{Mn}(\text{OH})_2$ :



being slow, sufficient time should also be allowed.

- (4) While adding the reagents and replacing the stopper, the bottle should be placed in a trough or basin as some liquid will always overflow.

#### Observations

Total volume of the sample taken	= 300 ml
Volume of reagents added during the preparation of iodine solution	= (0.7 ml $\text{H}_2\text{SO}_4$ + 0.2 ml $\text{KMnO}_4$ + 0.5 ml $\text{K}_2\text{C}_2\text{O}_4$ + 2 ml $\text{MnSO}_4$ + 3 ml alkaline KI) = 6.4 ml.

Volume of prepared solution (iodine) taken for titration	= 204.4 ml
--	------------

Mean volume of N/40 $\text{Na}_2\text{S}_2\text{O}_3$ used	= A ml
--	--------

#### Calculations

6.4 ml of the reagents have been added under such conditions that



approximately equal volume of the sample is displaced. This dilutes the sample and so a correction is needed. Volume of the original sample that will be equivalent to 204.4 ml of the prepared (diluted) solution is given by

$$\frac{\text{Total volume of the sample} - \text{volume displaced by reagents}}{\text{Total volume of the sample}} \times 204.4$$

$$= \frac{300 - 6.4}{300} \times 204.4 = 200 \text{ ml}$$

Thus the iodine content of 204.4 ml of the prepared solution (diluted sample) is equivalent to the D.O. of 200 ml of the original sample. Then using the normality equation

$$\begin{array}{ccc} N_1 V_1 & = & N_2 V_2 \\ \text{(Oxygen solution)} & & \text{(Hypo solution)} \end{array}$$

$$N_1 \times 200 = \frac{1}{40} \times A$$

$$\text{or } N_1 \text{ (Normality of the sample w.r.t. D.O.)} = \frac{1}{200} \times \frac{1}{40} \times A$$

$$\begin{aligned} \therefore \text{Strength} &= \frac{1}{200} \times \frac{1}{40} \times A \times 8 \text{ g/l} \\ &= A \text{ mg/l} = A \text{ ppm} \end{aligned}$$

### Exercises


59. What is the effect of the presence of oxidising impurities like  $\text{NO}_2^-$  and  $\text{Fe}^{3+}$  (if not removed) on the D.O. results?
60. How do reducing impurities such as  $\text{Fe}^{2+}$ ,  $\text{SO}_3^{2-}$ ,  $\text{S}^{2-}$ , etc., affect the D.O. determination?
61. What do you understand by the phrase fixation of dissolved oxygen?
62. Why is the  $\text{Na}_2\text{S}_2\text{O}_3$  solution of N/40 strength selected for titration?
63. State Henry's law for the solubility of a gas in a liquid. Outline the conditions under which the law is applicable.

### 3.4.2 Biochemical Oxygen Demand (BOD)



Micro-organisms can utilize carbohydrates, proteins and oils & fats as food and oxidize them to obtain energy for their life processes. Some bacteria can also utilize reduced inorganic materials like  $\text{Fe}^{2+}$ ,  $\text{S}^{2-}$  and ammonia as sources of energy. In the biological degradation (of sewage and other waste material) which is brought about by a diverse group of living organisms or bacteria, organic matter is first converted to fatty acids which, by successive oxidation at  $\beta$ -carbon atom, are 'broken down' into fragments consisting of acetic acid. When sufficient oxygen is present, that is in aerobic systems, oxygen is the ultimate electron acceptor which is reduced while organic




matter is being oxidised to  $\text{CO}_2$  and  $\text{H}_2\text{O}$  :




Inorganic materials like  $\text{S}^{2-}$  and reduced nitrogen ( $\text{NH}_3$  or  $\text{NH}_4^+$ ), if present, are oxidised to sulphate and nitrate:



When the availability of oxygen is insufficient (anoxic conditions), organic matter is oxidised by using nitrate as electron acceptor :






[Nitrate may also be reduced to the amine stage



giving odour resembling that of decaying rotten fish.]

Under strictly anaerobic conditions, i.e., in the absence of oxygen,  $\text{SO}_4^{2-}$ ,  $\text{PO}_4^{3-}$  and  $\text{CO}_2$ , whatever available, can act as electron acceptors and are reduced to  $\text{H}_2\text{S}$ ,  $\text{HS}^-$  (mercaptans—rotten-egg smell), phosphine (poisonous and wormy odour), methane (suffocating), etc.:



Sewage and other oxygen-demanding wastes are termed as water pollutants because :

- their decay leads to depletion of dissolved oxygen, which affects (and even kills) fish and other aquatic life,
- they produce annoying odours,
- they impair domestic and livestock water supplies by affecting taste, odours and colours, and
- they promote conditions favourable for the growth of infectious agents (pathogenic bacteria).

To avoid development of nuisance or septic conditions, sufficient oxygen must be present or supplied externally to maintain aerobic conditions throughout.

The amount of oxygen required by a mixed population of micro-organism in oxidising organic matter present in a sample, under strictly aerobic



conditions, is generally known as B.O.D., and is directly related to the extent of pollution (by sewage or other oxygen-demanding wastes).

The rate of bacterial oxidation at any instant is proportional to the amount of the oxygen-demanding wastes left at that instant, i.e., the reaction follows First Order Kinetics and theoretically should be completed in infinite time. It has however been found that nearly 70 to 80% of the total BOD is exerted in the first five days. The sample is therefore incubated for 5 days at 20°C (roughly a mean value of temperatures of natural bodies of water) and the BOD values are reported as BOD<sub>5</sub>. A polluted sample may consume more oxygen in 5 days than present in water (nearly 9 mg/l at 20°C) and so, before analysis, is diluted with a specially prepared 'Dilution water'. The diluted sample is taken in two bottles. The dissolved oxygen (D.O.) in one bottle is determined immediately and in the other after 5 days of incubation. The BOD of the sample is then given by

$$\text{BOD} = \frac{D_1 - D_2}{A} \times B \text{ mg/l} \quad (3.63)$$

where  $D_1$  = D.O. of the sample in mg/l at the start of the experiment

$D_2$  = D.O. of the sample in mg/l after 5 days

$A$  = ml of the sample before dilution

$B$  = ml of the sample after dilution.

### Exercises

64. 10 ml of a polluted water sample was diluted to 600 ml and equal volumes were poured into two B.O.D. bottles. D.O. in one bottle was determined immediately (Blank) by Winkler's method and 204.4 ml solution required 3.9 ml of N/40  $\text{Na}_2\text{S}_2\text{O}_3$ . The second sample was incubated for 5 days and in the D.O. determination, 204.4 ml solution required 2.1 ml of N/40  $\text{Na}_2\text{S}_2\text{O}_3$ . Calculate B.O.D. of the polluted water.
65. Outline the significance of B.O.D. measurement.
66. Why has the 5-day incubation period been selected for BOD determination?
67. What should be the composition of a good 'Dilution Water' for BOD determination?

### 3.4.3 Determination of Chemical Oxygen Demand (C.O.D.) of a Waste Water Sample

The COD is usually defined as the amount of oxygen used while oxidizing the organic matter content of a sample with a strong chemical oxidant under acidic conditions. The organic matter in the sample is related to the oxygen required (COD) in accordance with equation:





Since in the COD determination, the organic matter (both biologically oxidizable like glucose and biologically inert like cellulose) is completely oxidised to  $\text{CO}_2$  and  $\text{H}_2\text{O}$ , the COD values are greater than BOD values (which represent the amount of oxygen that bacteria need for stabilising biologically oxidizable matter).

### Significance


For samples from a specific source, COD can be related to BOD. The COD test is therefore widely used for measuring the pollutional strength of domestic and industrial wastes. Used in conjunction with the BOD test, it indicates the magnitude of the biologically resistant organic matter. The major advantage of the COD test is that the determination is completed in 3 hours, compared to the 5 days required for the BOD determination, and therefore steps can be taken to correct errors on the day they occur.

### Reagents Required


1. Standard potassium dichromate solution (N/4)
2. Standard ferrous ammonium sulphate solution (FAS N/4)
3. Silver sulphate-sulphuric acid reagent
4. Ferroin indicator solution.
5. Mercuric sulphate ( $\text{HgSO}_4$ ).

### Theory

A suitable aliquot of the sample is boiled with a known excess of  $\text{K}_2\text{Cr}_2\text{O}_7$  in presence of conc.  $\text{H}_2\text{SO}_4$ . The organic matter is oxidised to  $\text{CO}_2$  and  $\text{H}_2\text{O}$ :



The excess of dichromate left unused is titrated with FAS standard solution using ferroin as indicator:



The amount of  $\text{K}_2\text{Cr}_2\text{O}_7$  consumed corresponds to COD.

### Procedure

To 50 ml of the sample taken in a 500-ml reflux flask, add 1 g  $\text{HgSO}_4$  and some broken porcelain pieces or glass beads. Immerse the flask in cold water and slowly add 75 ml of  $\text{Ag}_2\text{SO}_4 - \text{H}_2\text{SO}_4$  reagent while continuously shaking the flask. Add 25 ml of N/4  $\text{K}_2\text{Cr}_2\text{O}_7$  solution. Mix the contents of the flask thoroughly. Fix the water condenser and reflux for 2 hours. Wash the condenser with distilled water into the flask. Cool and dilute to about 300 ml. Add 2 to 3 drops of Ferroin indicator and titrate against N/4 FAS



until the first sharp colour-change from blue green to reddish brown. Record the volume of FAS used as A ml.

### Blank Titration

Take a volume of distilled water, equal to that of the sample, in another reflux flask. Add the same amounts of reagents, reflux for 2 hours and titrate in the same way as in the sample titration. Record the volume of FAS used as B ml. COD of the sample corresponds to (B - A) ml of standard (N/4) FAS.

### Precautions

The addition of  $\text{Ag}_2\text{SO}_4 - \text{H}_2\text{SO}_4$  reagent to the sample is an exothermic process and may lead to loss of material. To avoid this, it is important to mix the reflux mixture slowly with shaking and the flask should be cooled during mixing. It is better to fix the reflux condenser in the flask and then add the major portion of the  $\text{Ag}_2\text{SO}_4 - \text{H}_2\text{SO}_4$  reagent through the open end of the condenser.

### Observations and Calculations

Volume of sample taken		= 50 ml
Volume of N/4 FAS used in the sample (test) titration		= A ml
Volume of N/4 FAS used in blank titration		= B ml
Therefore, Volume of N/4 FAS equivalent to $\text{K}_2\text{Cr}_2\text{O}_7$ used in satisfying COD		= (B - A) ml
	$N_1 V_1$	= $N_2 V_2$
	(sample)	(FAS)
$N_1 \times 50$	$= \frac{1}{4} \times (B - A)$	
or	$N_1$	$= \frac{(B - A)}{4 \times 50}$
Therefore,	C.O.D.	$= \frac{(B - A)}{4 \times 50} \times 8 \text{ g/l}$
		$= \frac{(B - A) \times 8 \times 1000}{4 \times 50} \text{ mg/l}$
		$= (B - A) \times 40 \text{ mg/l}$

### Exercises

68. What are the major sources of error in the above method ?
69. How are the above-mentioned errors minimised ?




### 3.5 Residual Chlorine and Chlorine Demand


Water is the chief vehicle of transmission for some diseases like dysentery, cholera, typhoid, etc. (called water-borne diseases), caused by pathogenic bacteria. Growth of other living organisms such as algae and fungi in water may be extremely harmful when such water is used for certain industrial purposes. Chlorination is an important disinfection process which serves to destroy or deactivate the disease producing and other harmful organisms.

Chlorination may produce adverse effects also. Phenols, if present in water, are converted into mono-, di-, or trichloro-phenols which impart unacceptable taste and odour to water. Some forms of aquatic life are adversely affected by chlorination of waters containing ammonia or amines. Humic substances which are present in most water supplies are converted into several chlorinated products, the most harmful of which is the carcinogenic chloroform ( $\text{CHCl}_3$ ). In spite of these adverse effects, chlorination has not been abandoned because of the immense benefits arising from it which far outweigh the risks involved.



Chlorine is applied to water in its elemental form ( $\text{Cl}_2$  gas or a concentrated solution of  $\text{Cl}_2$  in water) or as hypochlorite ( $\text{NaOCl}$  or bleaching powder). Chlorine reacts with water to produce hypochlorous acid which further dissociates to give  $\text{H}^+$  and  $\text{OCl}^-$ .




The relative amounts of  $\text{Cl}_2$ ,  $\text{HOCl}$  and  $\text{Cl}^-$  depend on the temperature and pH. At the pH of the most natural waters,  $\text{HOCl}$  and  $\text{Cl}^-$  predominate. Ammonia, formed by dissociation of  $\text{NH}_4^+$  ion impurity




present in water, is slowly attacked by  $\text{Cl}_2$  or  $\text{HOCl}$  to form small amounts of mono-, di- and trichloramines:



the mono- and dichloramines being important disinfectants. With higher concentrations of  $\text{Cl}_2$  (1.5 mole  $\text{Cl}_2$  per mole of  $\text{NH}_3$ ),  $\text{N}_2$  or  $\text{NO}_3^-$  are formed, depending upon pH, temperature and reaction time:







Chlorination beyond this stage (called Break-point chlorination) increases the amounts of  $\text{Cl}_2$ ,  $\text{HOCl}$  and  $\text{OCl}^-$  which are referred to as free chlorine residuals. While the free chlorine residuals are quickly dissipated in the distribution system, the chloramines (referred to as combined chlorine residuals) are stable. This affords longer contact time, thus lowering the concentration of the disinfectant required for equivalent destruction of bacteria. Chloramines act as chlorine reserves killing bacteria left during the initial treatment and guard against any inadvertent bacterial contamination at a later stage. Their presence is therefore particularly desired when water is to be transported over long distances. When a chlorinated water is devoid of combined chlorine residuals, a small amount of  $\text{NH}_3$  or ammonium salt is added after chlorination.

An overdose of chlorine not only increases the cost of disinfection but imparts an unpleasant taste to drinking water and is also injurious to health. For efficient disinfection of domestic water supplies, swimming pools and treatment of waste waters, measurement of both free and combined chlorine residuals is essential.






### 3.5.1 Determination of Total Chlorine Residuals (Iodometric Method)

#### Reagents Required


1. Standard sodium thiosulphate solution (N/100)
2. Glacial acetic acid
3. Potassium iodide
4. Freshly prepared starch solution.

#### Theory

When KI is added to water at pH 3-4, both free and combined chlorine residuals react to oxidise iodide to free iodine :



The liberated iodine is titrated with a standard solution of  $\text{Na}_2\text{S}_2\text{O}_3$ , using starch solution as indicator near the end-point:



#### Procedure

Pipet out 100 ml of the water sample into an iodine titration flask containing 1 g of KI and 2 ml of glacial acetic acid. Stopper the flask and



shake well to mix the solution. Rinse the stopper and the sides of the flask with distilled water (using a wash bottle) into the flask. Add  $\frac{N}{100}$   $\text{Na}_2\text{S}_2\text{O}_3$  solution from a burette slowly with constant shaking until the colour of the solution becomes very light yellow or straw yellow. Add 1 ml of freshly prepared starch solution and titrate further until the blue colour disappears. Record the volume of  $\text{Na}_2\text{S}_2\text{O}_3$  solution used as A ml. Take concordant readings.

#### Precautions

1. The titration should be completed rapidly in order to avoid atmospheric oxidation of iodide.
2. First disappearance of blue colour should be taken as the end-point.

#### Observations and Calculations

Volume of water sample taken for each titration = 100 ml

Concordant volume of  $\frac{N}{100}$   $\text{Na}_2\text{S}_2\text{O}_3$  used = A ml

$$\begin{aligned} N_1 V_1 &= N_2 V_2 \\ \text{(sample)} &\quad \quad \quad \text{(Na}_2\text{S}_2\text{O}_3\text{)} \\ N_1 \times 100 &= \frac{1}{100} \times A \end{aligned}$$

Therefore,  $N_1$  (Normality of sample w.r.t. total chlorine residuals) =  $\frac{1}{100} \times A \times \frac{1}{100}$

$$\begin{aligned} \text{Total chlorine residuals} &= \frac{1}{100} \times A \times \frac{1}{100} \times 35.5 \text{ g/l} \\ &= \frac{1}{100} \times A \times \frac{1}{100} \times 35.5 \times 10^3 \text{ mg/l} \\ &= 3.55 \times A \text{ ppm} \end{aligned}$$

#### Exercises

70. Why and how is pH adjusted between 3 and 4?
71. What are the common impurities that interfere in the detn.?

#### 3.5.2 Determination of Free Chlorine Residuals and Combined Chlorine Residuals (Chloramine and Dichloramine) in a Treated water (DPD-Ferrous Titrimetric Method)

##### Reagents Required

1. Standard ferrous ammonium sulphate solution (N/100 FAS)
2. Phosphate buffer (pH 6.2–6.5)
3. Potassium iodide
4. DPD indicator solution.



*Theory*

- (a) In the pH range 6.2 – 6.5, free chlorine residuals oxidise N, N-diethyl-p-diphenylenediamine (DPD) quantitatively to produce a red colour which can be titrated to a sharp colourless end-point by standard ferrous ammonium sulphate (FAS) solution.
- (b) If a small crystal of KI is added at this stage, monochloramine oxidises DPD to produce equivalent red colour which is immediately titrated with FAS.
- (c) Addition of more KI (about 1 g) produces more red colour due to the slow oxidation of DPD by dichloramine which is titrated with FAS after waiting for about 2 minutes.

*Procedure*

Add 100 ml of the sample to a titration flask containing 5 ml of phosphate buffer solution (pH 6.2 – 6.5) and 5 ml of DPD indicator solution. Mix and titrate rapidly with standard FAS until the red colour disappears. The volume of FAS (A ml) used corresponds to the amount of free chlorine residuals in the sample.

Add 1 crystal of KI to the above solution. Mix and rapidly titrate against FAS until the red colour is again discharged. The volume of FAS (B ml) consumed is equivalent to monochloramine present in the sample.

Add 1 g of KI to the above solution and mix well. Allow to stand for 2-3 minutes and titrate against FAS. The volume consumed (C ml) corresponds to the amount of dichloramine in the sample.

*Precautions*

1. After the addition of 1 crystal of KI, the solution should be immediately titrated with no loss of time as otherwise dichloramine may also react.

*Observations and Calculations*

- (a) Free chlorine residuals :

$$\text{Volume of sample taken} = 100 \text{ ml}$$

$$\text{Volume of } \frac{N}{100} \text{ FAS used} = A \text{ ml}$$

$$N_1 V_1 = N_2 V_2$$

$$(\text{sample}) \quad (\text{FAS})$$

$$N_1 \times 100 = \frac{1}{100} \times A$$

$$\text{or} \quad N_1 = \frac{1}{100} \times A \times \frac{1}{100}$$

$$\text{Amount of free chlorine residuals} = \frac{1}{100} \times A \times \frac{1}{100} \times 35.5 \text{ g/l}$$



$$= \frac{A \times 35.5}{100 \times 100} \times 10^3 \text{ mg/l}$$

$$= 3.55 \times A \text{ ppm}$$

(b) Combined chlorine residuals present as monochloramine

$$= 3.55 \times B \text{ ppm}$$

(c) Combined chlorine residuals present as dichloramine

$$= 3.55 \times C \text{ ppm}$$

### Exercises

72. Why is the pH control so important in this determination?

73. EDTA is added in the preparation of DPD indicator solution. What is its purpose?

### 3.5.3 Chlorine Demand

Chlorine reacts with a wide variety of inorganic and organic materials present in water. The demand of these impurities for chlorine has to be satisfied before chlorine becomes available for disinfection. The difference between the amount of chlorine applied to a water sample and residual chlorine is reported as *Chlorine Demand*. It depends on the nature of impurities present in the sample, the amount of chlorine applied, the amount of residual chlorine desired, contact time, pH and temperature. Chlorine demand can be determined by treating a series of aliquots of the water sample with known but varying dosages of chlorine or hypochlorite (such as bleaching powder) and determining the residual chlorine at the end of the contact period. This will give the dosage required for any desired residual at the temperature of the experiment.

### 3.5.4 Determination of the amount of Bleaching Powder required to disinfect a water sample by Horrock's Test


#### Reagents Required

1. Bleaching powder
2. Potassium iodide
3. Glacial acetic acid
4. Freshly prepared starch solution.

#### Theory

Increasing amounts of a solution of known concentration of bleaching powder are added to the same known volumes of the sample taken in a number of containers. After allowing sufficient time for disinfection to take place, a few crystals of KI and glacial acetic acid are added to each of the containers. This leads to liberation of iodine, in the containers in which disinfection is complete and there is residual chlorine, which is detected by the production of blue colour on addition of starch solution.





The method is approximate as no standard solutions are used and the residual chlorine is not measured quantitatively. However, the method is very quick and when conducted with care, it can lead to efficient disinfection. The procedure has been so designed that even a layman can conduct it easily, and make water safe for drinking.

### Procedure

Take seven glass containers or bottles marked at 100-ml level. Transfer one level spoonful (about 1 g) of bleaching powder to one of the containers, add a little distilled water and stir with a glass rod until it is converted into a paste. Add more distilled water to fill the container up to the mark and stir vigorously. Leave the solution to let the suspension settle down. Fill the remaining containers with water sample up to the mark. Number them as 1, 2, 3, 4, 5 & 6, with a glass marking pencil, and arrange in a row. Using a medicine dropper (delivering 20 drops per ml), transfer 1, 2, 3, 4, 5 & 6 drops of the prepared solution of bleaching powder to the containers numbered 1, 2, 3, etc., respectively. Stir thoroughly the contents of each container. Allow to stand for half an hour (contact period). Add to each container a few crystals of KI and 1 ml of glacial acetic acid followed by 1 ml of freshly prepared starch solution. Stir the contents gently with the rod and look for the development of blue colour. Note the container showing blue colour with minimum number of drops of the bleaching powder solution. If none of the containers shows a blue colour, throw the contents. Wash the containers thoroughly with distilled water and perform the test with 7, 8, 9, 10, 11, & 12 drops of the bleaching powder solution. Record the contact period and temperature.

### Precautions

- (1) While preparing the paste, care should be taken to break with a glass rod (preferably with a flattened tip) any lumps of the bleaching powder left.
- (2) The tip of the dropper should be clean and the drops should be added slowly so that they are fully formed.
- (3) Contact period for all the samples should be constant (the same), i.e., bleaching powder solution or KI and acetic acid should be added, as far as possible, simultaneously to all the samples.

*Note:* The test can be made more accurate by taking a known weight of the bleaching powder for preparing the solution.

### Observations and Calculations

Volume of water sample taken in each container	= 100 ml
Concentration of bleaching powder solution used	= 1 level spoonful (~ 1g)/100 ml
Contact period	= _____ minutes
Temperature of the experiment	= $t^\circ\text{C}$



Table

Sr. No. of the container	No. of drops of B.P. solution added	Appearance of blue colour	Minimum No. of drops producing blue colour
1	1	No	
2	2	No	
3	3	—	
4	4	—	(n. say)
5	5	Yes	
6	6	Yes	
—	—	—	
—	—	—	

1 level spoonful of B.P.  $\equiv$  100 ml of B.P. solution

$$= 100 \times 20 \text{ drops}$$

Volume of sample disinfected by n drops = 100 ml

" " " 1 drop =  $\frac{100}{n}$  ml

" " "  $100 \times 20$  drops =  $\frac{100 \times 2000}{n}$  ml  
 $= \frac{200}{n}$  litres

B.P. required for  $\frac{200}{n}$  litres of the sample = 1 level spoonful ( $\sim$  1 g)

" " 1 " " =  $\frac{1 \times n}{200}$  "

" "  $10^3$  " " =  $\frac{1 \times n}{200} \times 10^3$  "

= 5 n level spoonful

$\approx$  5 n g

### Exercises

74. What is meant by Chlorine Demand of a water sample ?
75. Name a few chlorine-reactable materials that may be present in water as impurities.
76. Describe the nature of the reactions which these substances undergo with chlorine.
77. Specify the optimum chlorine dosage, contact time and pH range for effective disinfection.



78. What is meant by stabilising the chlorine?
79. What is Break-point Chlorination? What is its significance?
80. What do you understand by Prechlorination and Post-chlorination?

### 3.6 Turbidity and Coagulation

The term turbidity is applied to finely divided particles suspended in water, due to which light passing into the sample is absorbed and scattered. Visual depth in such water is restricted. The turbidity of a water sample is related inversely to its 'clarity.' It is simply an optical property of the particles suspended in water and not a direct assessment of their amount present, since it is related to the size distribution of the particles. Turbidity in water may be of organic or inorganic origin. It is caused by suspended particles of clay, loam, sand, silt, decomposing food material, contamination with municipal or industrial waste water, organic coloured compounds, algae and other micro-organisms.

#### *Significance*

Consumers of municipal water supplies are always reluctant to accept even very slightly turbid waters as they often consider it to be polluted by domestic waste water—the cause of many water-borne diseases. Permissible turbidity for drinking water is between 5-10 units and preferably it should be less than 5. Turbidity makes filtration very difficult. To get good quality water, filters of special design have to be used, thereby increasing the cost. A high turbidity value of the filtered water points to faulty filter operation. When turbidity is due to contamination with sewage, disinfection is less effective because some of the pathogenic bacteria are enclosed in the sewage particles and escape the killing action of the disinfectant.

Measurement of turbidity is useful in deciding whether water from a particular source can be used without chemical coagulation. Turbidity measurement, before and after coagulation by different chemicals, is used to select the most effective and economical substance and to determine its optimum dose.

In the removal of suspended solids from domestic and industrial wastes of frequently changing composition, turbidity measurement, being much quicker than suspended solids determination, is especially useful to adjust the optimum dosages of chemicals required.

#### *Turbidity Standards*

Since turbidity is caused by a wide variety of materials, the following arbitrary standard has been chosen to compare turbidity of different waters: 1 unit turbidity is the turbidity produced by 1 part of fuller's earth in a million parts of distilled water (1 unit = 1mg  $\text{SiO}_2$ /l, and the size of particles of  $\text{SiO}_2$  used must lie within certain specific limits—the particles should pass through a 200-mesh sieve).

Standard suspensions of pure  $\text{SiO}_2$  were used originally to calibrate Jackson Candle Turbidimeter, which is now used for routine work and no standards are required. In this method, interference caused to the passage of light is measured visually and the results are reported as Jackson Turbidity Units (JTU).

The instrumental method which, instead, is based on the measurement of the



intensity of light scattered by turbidity using Nephelometry, gives different results which are reported in Nephelometric Turbidity Units (NTU).

### 3.6.1 *Determination of Turbidity between 25-1000 JTU by Jackson Turbidimeter*

#### *Procedure*

Shake the sample well and transfer 10-15 ml of it into a cool Jackson tube (made from colourless glass, with a flat, polished, optical glass bottom and calibrated for direct turbidity readings) and fix it in position in turbidimeter. Light the candle or bulb at the base. Pour slowly, through a funnel, additional portions of the sample into the Jackson tube and after each addition, view the lighted candle (or bulb) from above. Continue addition of the sample until the contour (outline) of the flame or bulb is no longer visible. Extinguish the flame (or switch off the bulb). Take out the Jackson tube and record turbidity in JTU units. Take out a small amount of the sample; place the tube in position, light the candle (or bulb) and adding very small portions of the removed sample at a time, approach the end-point very carefully. Take a number of readings and report the mean value.

#### *Precautions*

- (1) The Jackson tube should be kept clean, both inside and outside.
- (2) Scratching of the tube should be avoided.
- (3) The charred portion of the wick (if candle is used) should be trimmed and the distance of the flame from the bottom of the tube should be kept constant.

### 3.6.2 *Determination of Turbidity between 5-100 JTU with Bottle Standards*

#### *Procedure*

Take a number of glass bottles of same size, shape and colour characteristics. Place the sample in one bottle and a number of standard suspensions of varying turbidities (made by suitably diluting, with distilled water, a natural turbid water standardised with Jackson Turbidimeter) in other bottles. Look through the sides of the bottles (sample and standards) at the same object (ruled paper or printed matter) and compare the distinctness with which the object can be seen. The turbidity of the sample is equal to the turbidity of the standard that most closely produces the same interference to visual perception as the sample.

#### *Precautions*

- (1) As the number and size of particles changes with time, the standard suspensions must be frequently replaced.
- (2) The standards should be well shaken before use.
- (3) All the bottles (containing the sample and the standards) should be illuminated, well and equally, with a source of light so placed that no rays reach the eye directly.



**Exercises**


81. Distinguish between Jackson Turbidimetry and Nephelometric Turbidity.
82. What is meant by *Coefficient of Fineness* ? What is its significance ?
83. What is the Platinum Wire Method of Turbidity measurement ? What is its 'specific' use ?
84. Name the chemical added to the turbidity standards to prevent the growth of bacteria or algae.

**3.6.3 Coagulation**

Finely divided particles of colloidal dimensions, suspended in water, settle at a very slow rate and readily pass through the pores of the filter. To make sedimentation and filtration practicable, the size of the particles has to be increased. This is achieved by coagulation followed by flocculation.

*Coagulation* is the process of adding chemicals to destabilise particles in a colloidal dispersion while *Flocculation* is their subsequent enmeshment, by gentle and prolonged mixing, to form discrete, visible, suspended particles that settle under gravity alone and are easily filterable.

When aluminium and iron salts are added to water, multipositive hydroxo and polynuclear species of compounds are formed. [Model example of dinuclear species :



the solution becomes acidic].

$[\text{Al}_8(\text{OH})_{20}]^{4+}$  has been suggested to be the most effective species in coagulation.

The coagulant species are then readily absorbed on the surface of the suspended particles (particularly true for hydrophobic clay particles)—electrical attraction enhancing deposition. This causes decrease in the electrical charges and so the particles are destabilised and are in a position to agglomerate. Mixing or turbulence promotes collisions which result in lasting union. The progressively increasing mass of flocculent material produced by the hydrolysis of the coagulant may enmesh the turbidity particles and act like a 'sweep' as it settles.

In case of hydrophillic colloids (organic material—as in sewage) containing



polar groups like hydroxyl, carboxyl or phosphate, destabilisation is largely due to chemical combination with the hydrolysis products of the coagulant.

*3.6.4 To determine the minimum dose of a Coagulant required to coagulate a given sample by Jar Test and to compare the effectiveness of aluminium sulphate and ferric sulphate as coagulants for a given sample at room temperature*

#### *Significance*

A certain minimum dose of the coagulant must be added for effective coagulation. Additional doses are required for increased turbidity but the relation is not linear. While a smaller dose is required for very high turbidities with variable particle size, very low turbidities are difficult to remove. In addition, the process is influenced by a number of inter-related factors such as pH, colour, mineral content and composition, temperature, the duration and degree of agitation and the nature of the coagulant used. Therefore, the optimum dose and conditions cannot be predicted on the basis of the results of physical and chemical analysis of water and must be determined experimentally. Coagulation is widely used in lime-soda softening and in removal of colloidal silica from waters meant for domestic consumption or for many industrial uses.

Measurement of turbidity before and after the coagulation process and the amount of coagulant left (not removed) are used to control and evaluate the efficiency of coagulation.  $\text{FeCl}_3$ ,  $\text{Al}_2(\text{SO}_4)_3$  and  $\text{Fe}_2(\text{SO}_4)_3$  produce acid on hydrolysis (reaction 3.82). Thus, if the sample is acidic, either alkali should be added in the form of carbonate or lime, or  $\text{NaAlO}_2$  which produces alkali on hydrolysis ( $\text{NaAlO}_2 + 2 \text{H}_2\text{O} \rightleftharpoons \text{Al}(\text{OH})_3 + \text{NaOH}$ ) should be used as coagulant.

The visible result of coagulation is the formation of a deposit in the form of porous gelatinous flakes that settle at the bottom of the vessel. If this is not observed, no coagulation has taken place.

#### *Reagents Required*

1. Aluminium sulphate solution (1.5%)
2. Ferric sulphate solution (0.5%).

#### *Procedure*

1. Take 8 beakers of 500-ml capacity each.
2. Transfer, with a measuring cylinder, 250 ml of the given water sample into each beaker.
3. Divide the beakers into two sets and mark them, with a glass marking pencil, as  $\text{I}_1$ ,  $\text{I}_2$ ,  $\text{I}_3$ ,  $\text{I}_4$  and  $\text{II}_1$ ,  $\text{II}_2$ ,  $\text{II}_3$  and  $\text{II}_4$ .
4. Attach the first set of sample beakers to the stirring device (a laboratory flocculator).
5. Add alum solution (15 g  $\text{Al}_2(\text{SO}_4)_3 \cdot 18\text{H}_2\text{O}$ /litre) with a graduated micro-pipet in amounts of 0.25 ml, 0.5 ml, 0.75 ml and 1.0 ml into the beakers  $\text{I}_1$ ,  $\text{I}_2$ ,  $\text{I}_3$  and  $\text{I}_4$  respectively.
6. Stir the samples rapidly for about half a minute followed by 15-minute gentle stirring at a rate of about 40 rpm.



7. Remove the beakers from the stirring device and let stand for settling the flocs.
8. Observe the flocs after every 10 minutes and record the characteristics (as slight, flocculent, considerable or heavy) in a tabular form.
9. If no coagulation takes place within an hour, repeat the experiment with dosages of 1.25 ml, 1.50 ml, 1.75 ml and 2.0 ml of alum solution.
10. Repeat the whole process taking 0.25 ml, 0.5 ml, 0.75 ml and 1.0 ml of ferric sulphate solution (5 g  $\text{Fe}_2(\text{SO}_4)_3$ /litre), instead of alum solution, into the second set of four beakers and record the observations in the table.
11. Select the minimum dosage of the better coagulant.

*Observations and Calculations*

Volume of sample taken = 250 ml

Concentration of alum solution used = 15 g/l

Concentration of  $\text{Fe}_2(\text{SO}_4)_3$  solution used = 5 g/l

Sl. No. of beaker	Coagulant used	Coagulant dose (ml)	Characteristic of floc	Selected minimum dose
I <sub>1</sub>	Aluminium sulphate	0.25 ml		A ml
I <sub>2</sub>		0.50 ml		
I <sub>3</sub>		0.75 ml		
I <sub>4</sub>		1.00 ml		
I <sub>5</sub>		—		
I <sub>6</sub>		—		
—		—		
II <sub>1</sub>	Ferric sulphate	0.25 ml		B ml
II <sub>2</sub>		0.50 ml		
II <sub>3</sub>		0.75 ml		
II <sub>4</sub>		1.00 ml		
II <sub>5</sub>		—		
—		—		

Quantity of aluminium sulphate required = A ml/250 ml

$$= \frac{A \times 15}{1000} \text{ g/250 ml}$$

$$= 15 \times A \text{ mg/250 ml}$$

$$= 60 A \text{ mg/l}$$

Quantity of  $\text{Fe}_2(\text{SO}_4)_3$  required

$$= B \text{ ml/250 ml}$$

$$= \frac{B \times 5}{1000} \text{ g/250 ml}$$



$$= 5 \times B \text{ mg/250 ml}$$

$$= 20 B \text{ mg/l}$$

### Precautions

As far as possible, the time and rate of stirring should be maintained constant for all the samples.

### Exercises

85. Specify the advantages of using a coagulant.
86. What is a flocculant aid? Give one example.
87. What do you understand by 'Liquid Alum'?

## 3.7 Solids

The impurities present in a water sample, whether suspended or dissolved, that have a negligible vapour pressure at 105°C may be termed as 'Solids'. Solids may adversely affect the quality of water in a number of ways. While waters containing suspended solids are not at all acceptable for drinking purposes, it is desirable that dissolved solids may not be more than 500 mg/l. Higher concentrations may cause laxative or sometimes the reverse effect (constipation) upon travelling people whose bodies are not adjusted to such waters, but there appears to be no ill-effect on residents regularly using such waters.

Suspended solids are also objected to for bathing or recreational (swimming) purposes. Higher levels of suspended solids in lakes or streams inhibit the penetration of sunlight and promote conditions favourable for growth of pathogenic (disease causing) bacteria.

Both suspended and dissolved impurities cause priming and wet steaming and deposit sludge and scale in the boiler.

### 3.7.1. Classification

- (A) 'Total solids', reported in mg/l, is the amount of the residue left in the vessel after evaporation of a sample and its subsequent drying in an oven at a specified temperature. Total solids determination is the easiest test conducted on industrial wastes to have an idea of the extent of dissolved inorganic salts.
- (B) 'Total Suspended Solids' represent, in mg/l, the portion of the 'total solids' retained by a filter, and
- (C) 'Total Dissolved Solids', is the portion that passes through the filter.

The magnitude of the suspended solids and dissolved solids thus depends on factors like the type of the filter and its pore-size, the physical nature and the particle size of the suspended impurities, etc.

In drinking water, most of the matter is in the dissolved form. The



amount of suspended solids increases with the extent of pollution and is maximum in sludges, where the dissolved fraction becomes less important.

(D) *'Fixed Solids and Volatile Solids'*


'Fixed Solids' is the term applied to the residue of total, suspended or dissolved solids after ignition for a specified time at a specified temperature. The weight loss on ignition is called 'Volatile Solids'. If the ignition is conducted at a temperature at which

- (i) the organic matter is completely converted into  $\text{CO}_2$  and  $\text{H}_2\text{O}$ , and
- (ii) there is minimum loss of inorganic substances due to decomposition and volatilization,

then the loss in weight is approximately equal to the organic content of the solid fraction of waste-water, activated sludge or industrial wastes.

The ignition is therefore usually conducted at  $550 \pm 50^\circ\text{C}$  and the only sources of error are

- (a) decomposition of thermally unstable  $\text{MgCO}_3$  :



and (b) volatilisation of ammonium salts not removed during drying. However, in the test on suspended solids, the inorganic dissolved salts are removed during filtration and so no error is caused. The volatile matter content of suspended solids is usually more than three-fourths whereas that of dissolved solids is very very small.

The results of the test are used to control aeration in the activated sludge process and form the basis for the design and operation of sludge digestion, vacuum-filter and incineration units in Sewage Treatment and Disposal.

(E) *'Settleable Solids'* is the material settling out of suspension. It depends on the method used and the time allowed for settling. It represents the suspended solids that are coarse and have specific gravity higher than that of water. The term is usually applied to sewage and indicates the amount of sludge that may be obtained in the sedimentation tank. The test is widely used in deciding the necessity of a sedimentation unit in the Sewage Disposal System. The measurement is also useful in predicting the physical behaviour of industrial and municipal wastes being drained into natural bodies of water.

### 3.7.2. Determination of 'Total Solids' (dried at $103\text{--}105^\circ\text{C}$ ) in a water sample

#### Procedure

Transfer a suitable aliquot (corresponding to about 0.1 g of dissolved matter) of the well-mixed sample to a dried (at  $103\text{--}105^\circ\text{C}$  for 1 hour; dry at  $550 \pm 50^\circ\text{C}$  if volatile solids are to be measured) and preweighed nickel (or platinum) crucible and evaporate to dryness on a water bath. Dry in an electric oven at  $103$  to  $105^\circ\text{C}$  for 1 hour, cool in a desiccator and weigh.



Repeat the process of drying, cooling and weighing until the weight loss is less than 4% of the previous weight.

#### Observations and Calculations

Let the volume of sample taken	= V ml
Weight of empty crucible (dried at 103 – 105°C)	= $w_1$ g
Weight of crucible + residue (dried at 103 – 105°C)	= $w_2$ g
Therefore, Weight of solids in V ml of the sample	= $(w_2 - w_1)$ g
and 'Total Solids'	= $\frac{w_2 - w_1}{V} \times 10^3$ g/l
	= $\frac{w_2 - w_1}{V} \times 10^3 \times 10^3$ mg/l
	= $\frac{w_2 - w_1}{V} \times 10^6$ ppm

#### Precautions

- (1) To keep the crucible clean, (i) it should be supported on a glass or porcelain ring with a flange on the water bath during evaporation.  
(ii) The outer surface of the crucible should be wiped before placing it in the oven for drying.
- (2) If the determination is to be completed in a short span of time, the volume of the sample should be reduced by gentle boiling on a hot plate before transferring the crucible to water bath. However, care should be taken to avoid spattering.

#### 3.7.3. Determination of 'Total Suspended Solids' dried at 103-105°C Procedure

Mix the sample well. Filter under suction a known volume through a glass-fiber filter disc previously washed and dried at 103-105°C to constant weight ( $550 \pm 50^\circ\text{C}$  for volatile content of suspended solids). Wash with distilled water. Continue suction to completely drain the water. Remove the filter disc, place it on a flat aluminium sheet for support and dry in an oven at 103-105°C for 1 hour. Cool in a desiccator and weigh. Repeat the drying process to get constant weight.

#### Observations and Calculations

Let the volume of the sample filtered	= V ml
Weight of the dried (103–105°C) glass filter disc	= $w_1$ g
Weight of filter disc + suspended solids, dried at 103–105°C	= $w_2$ g



Therefore, weight of suspended solids in V ml of the sample

$$= (w_2 - w_1) \text{ g}$$

and 'Total Suspended Solids'


$$= \frac{w_2 - w_1}{V} \times 10^3 \text{ g/l}$$

$$= \frac{w_2 - w_1}{V} \times 10^3 \times 10^3 \text{ mg/l}$$

$$= \frac{w_2 - w_1}{V} \times 10^6 \text{ ppm}$$

### 3.7.4 Determination of 'Total Dissolved Solids' dried at 180°C

Drying at 180°C removes most of water of crystallization



and some CO<sub>2</sub> due to conversion of bicarbonates into carbonates and their partial oxidation to oxides. Evaporation followed by drying at 180°C usually gives results closer to those obtained from complete analysis for mineral species than the results obtained by drying at 103-105°C.

#### Procedure

Transfer the filtrate<sup>1</sup> obtained in experiment 3.7.3. to a dried [180°C for 1 hour; dry at 550 ± 50°C for volatile content of dissolved solids] and weighed platinum crucible and evaporate to dryness on a steam bath. Dry at 180°C for 1 hour in an oven, cool in a desiccator and weigh. Repeat the drying process until there is no further loss in weight.

#### Observations and Calculations

Let the volume of the sample filtered

$$= V \text{ ml}$$

Weight of dried (at 180°C) empty crucible

$$= w_1 \text{ g}$$

Weight of crucible + residue, dried at 180°C

$$= w_2 \text{ g}$$

Therefore, weight of dissolved solids in V ml of the sample

$$= (w_2 - w_1) \text{ g}$$

and 'Total Dissolved Solids'

$$= \frac{w_2 - w_1}{V} \times 10^3 \text{ g/l}$$

$$= \frac{w_2 - w_1}{V} \times 10^3 \times 10^3 \text{ mg/l}$$

$$= \frac{w_2 - w_1}{V} \times 10^6 \text{ ppm}$$

Note 1: If a glass fibre filter disc is not available, a Gooch crucible with a filter-mat prepared from glass fibre or asbestos fibre may be used for filtration.



### 3.7.5. Determination of 'Fixed' and 'Volatile' Solids

#### Procedure

Ignite the residue obtained in experiments 3.7.2, 3.7.3 or 3.7.4 in a muffle furnace at a temperature of  $550 \pm 50^\circ \text{C}$ . Cool the crucible or the filter disc, as the case may be, in a desiccator and weigh. Finish the ignition to constant weight.

#### Precautions

- (1) The temperature should be strictly controlled as higher temperatures lead to the decomposition of inorganic matter.
- (2) Before placing the sample in the muffle furnace, destroy all inflammable material by controlled firing of the sample with bunsen flame. This will eliminate mechanical losses due to decomposition.

#### Observations and Calculations

Let the volume of sample taken	= V ml
Weight of dried filter disc or crucible	= $w_1$ g
Weight of filter disc or crucible + residue (dried)	= $w_2$ g
Weight of filter disc or crucible + residue, after ignition	= $w_3$ g
Weight of total solids, suspended solids or dissolved solids as the case may be	= $(w_2 - w_1)$ g
Weight of 'Fixed Solids' left after ignition	= $(w_3 - w_1)$ g
Weight of 'Volatile Solids' (weight loss on ignition)	= $(w_2 - w_1) - (w_3 - w_1)$ = $(w_2 - w_3)$ g

Therefore, 'Fixed Solids' (of total, suspended  
or dissolved matter, as the case  
may be)

$$= \frac{w_3 - w_1}{w_2 - w_1} \times 100\%$$

'Volatile Solids'

$$= \frac{w_2 - w_3}{w_2 - w_1} \times 100\%$$

### 3.7.6 Determination of 'Settleable Solids' by Imhoff Cone

#### Procedure

Mix the sample well and pour it into Imhoff cone up to 1-litre mark. Leave it undisturbed for 45 minutes, gently stir the sides of the cone with a glass rod and let the material settle for another 15 minutes. Record the volume of the material that settles and report the result in ml per litre.



*Precaution*

The volume of any liquid pockets present between large particles should be estimated and subtracted from the volume of settled solids. Any floating material completely separated from the settled material should not be included in the settleable solids.

*Observations and Result*

Volume of the sample taken

= 1 litre

Volume of solids settled

= V ml

Settleable solids

= V ml/litre



---

## Lubricating Oils, Greases and Emulsions

The resistance to motion that operates when one solid surface is moved tangentially with respect to another solid surface, with which it is in contact, is known as *Frictional Resistance*, and results in considerable loss of energy and damage to the contacting surfaces.

But friction is not all that useless. An innumerable number of processes of everyday life — lighting a match stick, walking, starting or stopping of a vehicle, gripping objects by hand, and what not — are dependent for their effectiveness on the presence of friction in large enough amounts. When friction is less, slippery conditions exist such as walking on sand, climbing up an oiled staff, etc.

In addition to the Van der Waals forces of attraction (molecular forces of cohesion) operating between the molecules of the contacting surfaces, resistance to motion is caused by inter-locking of minute projections—asperities or peaks, may be of the order of  $1000 \text{ \AA}$  (quite large when considered on molecular scale)—existing on the surfaces of even the smoothest objects. As one body moves past the other, some of the peaks are broken off, leading to wear and tear of the surface. Friction generates heat (highly localised at the points of contact between the rubbing surfaces) and coupled with high pressure developed even under small loads (as the actual points of contact are very small as compared to the apparent contact area between the objects) causes fusion of the material at the peaks and accounts for the formation of welded junctions. If the relative motion of the bodies is to be maintained, additional force is required to break these welded junctions which in turn generates more heat. The generation of heat is therefore a self-accelerating process and may eventually lead to large scale seizure and bring the moving bodies to a grinding halt.

The losses due to frictional resistance form a substantial part of the total energy consumption of mankind. In order to conserve the depleting energy reserves, it is essential that the frictional resistance be brought down to the optimum. Friction can be reduced by

- (i) decreasing the roughness of the surfaces involved,
- (ii) proper design of the moving parts,
- (iii) using surfaces of low coefficient of friction, or
- (iv) interposition of a substance of low shear strength between the moving surfaces. The substance that is used for this purpose is called a *Lubricant* and the process of reducing friction by use of a lubricant is known as *Lubrication*.



In addition to reducing energy losses and wear and tear of the moving surfaces, a lubricant is usually called upon to perform one or more of the following inter-related functions:

- (a) To act as a heat dissipating medium (coolant)
- (b) To form a seal (to prevent leakage, to keep out dirt)
- (c) To act as a medium for power transmittal (hydraulic)
- (d) To control corrosion (prevent rust)
- (e) To dampen shock (dissipation of mechanical energy through fluid friction—dash pots, gears, etc.)
- (f) To act as detergent or remove contaminants (flushing action to remove sludges from IC Engines)
- (g) To act as electric insulator (transformers, switch gears).

Depending upon the operating conditions and the lubricant characteristics, a lubricant may form a fluid film ( $\sim 1000 \text{ \AA}$  thick) in between the moving surfaces thereby removing all points of contact between them (Hydrodynamic or Fluid Film Lubrication). Solid friction is completely substituted by fluid friction and the coefficient of friction (0.001-0.01) is governed by viscosity of the fluid.

Under conditions of high load, low speed, or when the lubricant has a low viscosity, it may be squeezed out of position. Lubrication is then maintained by a very thin film (only a few molecules thick) of the lubricant adsorbed on the surface (Boundary Lubrication). The moving surfaces are not completely separated but their points of contact are considerably decreased. The coefficient of friction depends on the sticking characteristics (Oiliness) of the lubricant and is much higher (0.05-0.15) than in the case of hydrodynamic lubrication.


When the pressure and temperature are enormously high, even the boundary film may break. Lubrication under such conditions is maintained by Extreme Pressure Additives—certain substances added to the lubricant which, under the conditions of extreme pressure and temperature, react with the solid surface in question producing compounds having low shear strength, thus reducing the friction.

A wide variety of materials—air, liquids (animal and vegetable oils, mineral oils, synthetic oils), emulsions (oil-in-water and water-in-oil), suspensions (aquadag and oildag), semi-solids (greases) and solids (graphite, molybdenum disulphide, etc.)—have been employed for lubrication purposes.

#### 4.1 Oils

'Fatty' oils of vegetable and animal origin, such as olive oil, palm oil, rapeseed oil, linseed oil, cottonseed oil, castor oil, tallow oil, lard oil, sperm oil, seal and whale oils were the first to be used. They are usually the mixtures of mixed glycerides of saturated and unsaturated long chain acids and can be represented by





These oils are called 'Fixed' oils as they cannot be distilled without decomposition. They have good oiliness but

- (a) are costly
- (b) easily undergo oxidation, get polymerised and thickened, and
- (c) have a tendency to get hydrolysed in presence of water or moisture.

So they are now used only to a limited extent in the manufacture of greases and as additives to improve the oiliness of other lubricants. They have largely been replaced with cheap, more easily and abundantly available and more stable mineral oils obtained by refining of petroleum. Chemically, mineral lubricating oils are mixtures of hydrocarbons ( $\text{C}_{12}\text{--C}_{50}$ ), and may contain only a small amount of oxygen, present as impurity, while this element is the main constituent of fatty oils.

Selection of a lubricant for a particular job is a highly professional task and depends on such a wide variety of factors as the design of machine, the operating conditions (temperature, pressure, speed of movement, the duration for which the machine is to be used continuously, the nature of the environment), mode of application of the lubricant and its physical and chemical characteristics. It is now universally realised that the physical and chemical properties such as viscosity, specific gravity, flash point, volatility, acid value, saponification value, iodine value, etc., as measured in the laboratory, do not indicate exactly how a lubricant will behave under the operating conditions. These tests are therefore mainly used in the classification of and specifications for the type of lubricant required. They are also helpful in comparing the composition and evaluating the potential of the commercially available products. For a reasonably good prediction, the properties measured in the laboratory should be correlated to the service conditions expected to be met with in actual use. It is therefore desirable that variation of these characteristics with temperature, load, etc., and the extent and nature of possible contaminants should be studied. The suitability has finally to be established under the working conditions.

Usefulness of tests increases if test results can be compared directly with those obtained by others. This will be possible if the tests are performed in accordance with universally accepted common specifications. The majority of the tests have been standardised by British Institute of Petroleum (IP) and by American Society for Testing and Materials (ASTM). A few of these tests are outlined below.

## 4.2 Viscosity and Viscosity Index

### Significance

Viscosity is a measure of flowability at definite temperatures. The flow



properties of oils influence the rate of production of an oil-well, the transport of crude oil and refined products in pipelines and the performance of an oil as a lubricant in a machine.

Viscosity is the single most important property of the lubricating oils which determines their performance under the operating conditions. A lubricating oil should have sufficient viscosity to enable it to stay in position. On machine parts moving at slow speeds under high pressures, a heavy oil (high viscosity) should be used as it better resists being squeezed out from between the rubbing parts. Light oils (low viscosity) can be used, however, when lower pressures and higher speeds are encountered (since high speed permits a good oil wedge to form) and should be preferred as they do not impose as much drag on high speed parts as heavy oils do. In fact, under hydrodynamic lubrication, solid friction is completely substituted by fluid friction and so the frictional resistance encountered depends directly on the viscosity of the oil. Therefore, for minimum friction the thinnest (least viscous) oil that will stay in position should be used.

#### *Change of viscosity with temperature: Viscosity Index*

With rise in temperature, forces of cohesion between the molecules of a fluid are weakened, resulting in a decrease in viscosity. When the same lubricant has to function satisfactorily at widely varying temperatures (as is encountered in hydraulic systems, crankcases of internal combustion engines, automatic transmissions and gear cases and portable air compressors), the variation of its viscosity with temperature must be negligibly small. Otherwise, the lubricant may become very thin at higher temperatures (usually above 200°C during take off or landing of an aircraft) and may be squeezed out of position; or it may become highly viscous at very low temperatures (at times about -50°C, when the oil is pumped into aircraft engines in colder regions of the world) and may even cease to flow.

The variation of viscosity with temperature is either indicated by Viscosity-Temperature Curves (V-T curves) or measured on an arbitrary scale known as *Viscosity Index* (V.I.).

V.I. represents the average decrease in viscosity of an oil per degree rise in temperature between 100°F and 210°F. The viscosity (at 100°F) of the oil whose V.I. is to be calculated is compared with that of two standard oils, having the same viscosity at 210°F as the oil under test. One of these reference oils is chosen from a standard set made from Pennsylvania crude (consisting mainly of paraffins and showing a relatively small decrease in viscosity with rise in temperature) and arbitrarily assigned a V.I. of 100; the other is chosen from a standard set made from Gulf-Coast crude (consisting mainly of alicyclic hydrocarbons or naphthenes and exhibiting a relatively large variation in viscosity with temperature) and arbitrarily assigned a V.I. of 0 (zero). Mathematically,

$$\text{Viscosity Index} = \frac{L - U}{L - H} \times 100, \quad (4.1)$$



- where  $U$  = viscosity at  $100^{\circ}\text{F}$  of the oil whose V.I. is to be determined  
 $L$  = viscosity at  $100^{\circ}\text{F}$  of an oil of zero V.I. having the same viscosity at  $210^{\circ}\text{F}$  as the oil whose V.I. is to be determined  
 and  $H$  = viscosity at  $100^{\circ}\text{F}$  of an oil of 100 V.I. having the same viscosity at  $210^{\circ}\text{F}$  as the oil whose V.I. is to be calculated.

An oil whose viscosity changes rapidly with change in temperature has a low V.I. (the slope of V-T curve is high) while the one whose viscosity changes only slightly has a high V.I. (the V-T curve is flatter). Addition of linear polymers increases V.I. and oils with V.I. higher than 100 have been prepared. Methods to calculate values of V.I. higher than 100 are also available.




Fig. 3 Viscosity-temperature curves for the standards (L & H) and the oil under test (U).

#### 4.2.1 Determination of Viscosity of the given oil with Redwood Viscometer Theory

The Absolute or Dynamic viscosity is the tangential force per unit area required to move one horizontal plane of the fluid at unit velocity with respect to another maintained at a unit distance apart by the fluid. When the force is  $1 \text{ dyne/cm}^2$ , the distance between the layers or planes is  $1 \text{ cm}$  and the velocity gradient is  $1 \text{ cm/sec}$ , the viscosity is  $1 \text{ poise}$ . This being a large unit, absolute viscosity is more commonly expressed in centipoise ( $= \frac{1}{100} \text{ poise}$ ). The viscosity, also known as coefficient of viscosity,  $\eta$ , of water at  $20^{\circ}\text{C}$  is  $1.002 \text{ centipoise}$ .

When a liquid is made to flow through a capillary tube by a pressure gradient, and the time for a given volume to flow along the tube is measured, then at constant temperature, the coefficient of viscosity,  $\eta$ , is given by Poiseuille's equation

$$\eta = \frac{\pi P r^4 t}{8 V L} \quad (4.2)$$



where  $P$  = pressure difference between the ends of the tube  
 $L$  = length of the tube  
 $r$  = radius of the tube  
 $t$  = time in seconds  
 $V$  = volume of the liquid flowing through the tube in  $t$  seconds.

When the 'Inlet correction' and the 'Kinetic Energy Correction' are incorporated, the above equation takes the form

$$\eta = \frac{\pi P r^4 t}{V (L + k_1 r)} - \frac{V \rho k_2}{8 \pi (L + k_1 r) t} \quad (4.3)$$

where  $\rho$  is the density of the liquid and  $k_1$  and  $k_2$  are constants which depend on the form of the apparatus and are determined experimentally ( $k_1 = 0.16$ ,  $k_2 = 1.15$ ).

For accurate measurements on mineral oils, glass capillary viscometers are used. The driving force is provided by the head of the test oil flowing vertically down the tube and is given by

$$P = h \rho g, \quad (4.4)$$

where  $h$  is the mean height of the oil. The tube dimensions are so chosen that  $k_1 r$  in equation (4.3) becomes negligible as compared to  $L$ , so that

$$\eta = \frac{\pi h \rho g r^4 t}{8 V L} - \frac{V \rho k_2}{8 \pi L t} \quad (4.5)$$

For a particular instrument (Viscometer), the head of the oil is maintained at the same height  $h$ , and the time  $t$  in secs. for the flow of a fixed volume of the oil through the capillary of fixed dimensions is measured. Then  $h$ ,  $g$ ,  $r$ ,  $V$  and  $L$  all become constant and equation (4.5) is reduced to

$$\eta = C \rho t - \frac{B \rho}{t} \quad (4.6)$$

Dividing both sides by  $\rho$ , we get

$$\frac{\eta}{\rho} = C t - \frac{B}{t} \quad (4.7)$$

$$\approx C t \quad (4.8)$$

when  $t$  is very large. The time  $t$  in seconds measured experimentally is reported as Relative Viscosity and its magnitude depends on the viscometer used and the volume of the liquid that flows through the tube of the viscometer. Therefore, while reporting the relative viscosities of oils, the viscometer used must be specified.

The quantity  $\eta/\rho$ , the ratio of absolute viscosity to density of the liquid is known as Kinematic Viscosity. It is denoted by  $\nu$  and is expressed in centistokes when  $\eta$  is expressed in centipoise. The viscometers are usually engraved with the constants  $B$  and  $C$  such that when  $t$  is in seconds,  $\nu$  is in centistokes. The kinematic viscosities are thus independent of the viscometer used.



If measurements are made on two different liquids using the same viscometer, from equation (4.8) we get

$$\frac{\eta_1}{\rho_1} = C t_1 \quad (4.9)$$

and

$$\frac{\eta_2}{\rho_2} = C t_2 \quad (4.10)$$

where  $\eta_1$ ,  $\rho_1$  and  $t_1$  are the absolute viscosity, density and the time of flow of a fixed volume respectively for the first liquid and  $\eta_2$ ,  $\rho_2$  and  $t_2$  the corresponding values for the second liquid. Dividing equation (4.9) with (4.10) and rearranging, we get

$$\eta_1 = \eta_2 \cdot \frac{\rho_1 t_1}{\rho_2 t_2} \quad (4.11)$$

Thus knowing  $\eta_2$ , the absolute viscosity of one liquid,  $\rho_1$  and  $\rho_2$ , the densities of the two liquids at the temperature of the experiment and measuring  $t_1$  and  $t_2$ , the absolute viscosity of the other liquid can be calculated.

### Redwood Viscometers

Redwood viscometers are available in two sizes—No. 1 (Universal) and No. 2 (Admiralty). The two viscometers, RW1 and RW2, are identical in principle, shape and method of testing a sample. The difference lies in the dimensions of the discharge capillary (tube/jet/orifice):

Viscometer	Dimensions of jet	
	Diameter	Length
RW1	1.62 mm	10 mm
RW2	3.8 mm	50 mm

The rate of discharge of the oil through RW2 is nearly 10 times the discharge through RW1 and so the RW2 receiving-flask is designed with a wider mouth.

RW1 is commonly used for light or thin oils (e.g., kerosene, mustard oil, etc.). For highly viscous liquids (e.g., fuel oil, mobile oil, glycerol, etc.), when the flow time with RW1 may exceed 2,000 seconds, RW2 is used.

### Procedure

Level the viscometer with the help of levelling screws. Fill the outer bath with water and connect to electric mains. Clean the oil cup and the discharge jet with xylol followed by passing a small amount of the test oil through the jet, using a plunger. Place the ball valve on the agate jet to close it and pour the test oil into the cup to such a level that the metal indicator (pointer) fixed on the wall of the oil cup just dips in the oil. Insert a thermometer and a stirrer and cover with lid. Keep stirring the water in the bath and the oil in the cup and adjust the bath temperature until the oil attains the desired constant temperature. Place a clean and dry Kohlrausch



flask (marked to 50-ml capacity) immediately below and directly in line with the discharge jet (Figure 4). Remove the ball valve with one hand, simultaneously starting the stop watch with the other. Oil from the jet flows into the flask. Stop the timer when the lower meniscus of the oil reaches the 50-ml mark on the neck of the receiving flask. Record the time elapsed in seconds. Repeat the experiment to take a number of readings and report the mean value in seconds (Relative viscosity) mentioning the viscometer used and the test temperature.




Fig. 4 Redwood Viscometer.

- |                                  |                                  |
|----------------------------------|----------------------------------|
| A—Levelling screw                | B—Water bath                     |
| C—Heating coil                   | D—Brass oil cup                  |
| E—Agate jet                      | F—Metallic ball valve            |
| G—Metal indicator                | H—Lid                            |
| I—Oil stirrer                    | J—Water bath stirrer blade       |
| K—Water outlet                   | L—Water inlet                    |
| M—Kohlrusch flask                | T <sub>1</sub> —Test thermometer |
| T <sub>2</sub> —Bath thermometer |                                  |

### Precautions

- (1) Before testing, the oil should be filtered through muslin cloth or a 100-mesh wire-strainer to remove solid particles that may otherwise clog the jet. Moisture also clogs the jet and if present, the sample should be filtered through lintless filter paper.
- (2) The receiving flask should be placed in such a way that the oil stream from the orifice (jet) strikes the neck of the receiving flask and does not cause foaming.



- (3) To prevent the oil from overflowing, the jet valve should be closed immediately after stopping the timer.
- (4) After each reading, oil should be completely drained out of the receiving flask. The flask should preferably be washed with xylol and dried before repeating the test.
- (5) The test may be expedited by preheating the oil sample, before straining, in an aluminium cup (to not more than 3°F higher than the temperature of the test.)

### Exercises

88. What is meant by 'Inlet Correction'?
  89. What is the minimum Efflux Time (Flow time or Discharge time ) recommended for (Redwood) Viscometers ?
  90. The viscosity of an unknown oil was measured with Saybolt Universal Viscometer (S.U.V.) at temperatures 100°F and 210°F and was found to be 600 seconds and 60 seconds respectively. Calculate the Viscosity Index (V.I.) of the oil using the following table:
- | Name of the oil      | V.I. | S.U.V. seconds |          |
|----------------------|------|----------------|----------|
|                      |      | at 100°F       | at 210°F |
| 1. Pennsylvanian oil | 100  | 420            | 60       |
| 2. Gulf oil          | 0    | 780            | 60       |
91. How does the viscosity of a liquid vary with rise in temperature ?
  92. What is meant by 'all weather lubricants' ?
  93. Give some examples of lubricants that have high Viscosity Index.
  94. How is the Viscosity Index of a lubricating oil improved ?
  95. What is meant by the term 'Viscous-Static' ?
  96. How can a viscous-static lubricant be prepared ?

### 4.3 Cloud and Pour Points

Lubricating oils derived from petroleum usually contain dissolved paraffin wax and other asphaltic or resinous impurities, their amounts depending on the efficiency of dewaxing and refining process used. These impurities tend to separate out of the oil at lower temperatures. When a petroleum oil is chilled under specified conditions, the temperature at which paraffin wax or other solidifiable materials, normally dissolved in oil, begin to separate out from solution in the form of minute crystals, causing the oil to become less transparent, cloudy or hazy in appearance, is known as the Cloud Point of the oil.

If the cooling is continued further, the amount of the separating material increases and a stage is reached when the oil solidifies and stops flowing. The lowest temperature at which an oil will flow or pour under prescribed



conditions, when it is cooled undisturbed at a fixed rate, is called its Pour Point.

The cloud point determination is limited only to transparent oils; otherwise there may be slight variation in results due to the human error involved, since the decrease in transparency is to be visually observed.

### *Significance*

Cloud point of a lubricant to be applied by a capillary-feed system or wicking arrangement must be low so that the oil flow does not stop due to deposition of crystals of wax in the capillary or wick interstices. Cloud point is helpful in identifying the temperatures at which wax separation may clog the filter screens in the fuel intake system of diesel engines. Oils of naphthenic type, which are almost wax-free, show very low cloud points and this fact may be useful in identifying the source of the oil.

Pour point is more important since in the lubrication of any machine subjected to low temperature, the lubricant must flow freely, especially during the start-up period. A high pour point may lead to solidification of the lubricant that may cause jamming of the machine. Pour point also establishes the lowest temperature at which an oil can be transferred by pouring or below which, because of extremely poor mobility of the oil, lubrication by gravity flow process is less reliable.

#### *4.3.1 Determination of Cloud Point of an Oil*

Bring the oil sample to be tested to a temperature at least 25°F above the expected cloud point. If the sample contains moisture, dry it by shaking with a little anhydrous sodium sulphate followed by filtration through dry lintless filter paper. Pour the clear oil into the test jar upto the etched mark (or into a flat-bottom glass tube about 3 cm in diameter and 12 cm high to a depth of about 5 cm). Tightly close the jar with a cork carrying a thermometer with its bulb touching the bottom of the jar (Figure 5). Insert the test jar inside a holding jacket (made of glass or copper) which is immersed in a freezing mixture suitable for obtaining the desired temperature. After every 2°F fall in temperature of the oil, take out the test jar from the jacket, inspect for cloudiness and immediately replace it in the jacket. Record the temperature at which such inspection first reveals a distinct cloudiness in the oil near the bottom of the jar and report it as the cloud point.

#### *4.3.2 Determination of Pour Point of an Oil*

Proceed as in the cloud point test with the difference that the thermometer bulb is just completely immersed in the oil, instead of touching the bottom (Figure 5). Starting at a temperature about 20°F above the expected pour point, take out the jar after every 5°F fall in temperature and tilt it just enough to see any movement of the oil. Immediately replace the jar in the jacket. At a point where the oil in the jar shows no movement on tilting, hold the jar in a horizontal position for 5 seconds. If there is some movement of the oil, replace the jar immediately in the jacket and repeat the test for



flow after further  $5^{\circ}\text{F}$  fall in temperature. Continue the test until no movement of the oil is observed when the test jar is held in a horizontal position for exactly 5 seconds. Record the reading on the test thermometer as Solid Point. Add  $5^{\circ}\text{F}$  to this temperature to get the pour point.




Fig. 5 Cloud point and Pour point apparatus.

- |                                  |                                  |
|----------------------------------|----------------------------------|
| A—Freezing mixture               | B—Cork disc                      |
| C—Glass or Copper jacket         | D—Support for holding the jacket |
| E—Test jar                       | G—Air gap                        |
| F—Ring gasket                    | T <sub>1</sub> —Test thermometer |
| H—Cork                           |                                  |
| T <sub>2</sub> —Bath thermometer |                                  |

### Precautions

- (1) The test jar should not touch the jacket. This is achieved by placing a cork disc at the bottom of the jacket and using a ring gasket around the test jar.
- (2) The complete operation of the removal and replacement of the test jar should be completed within 3 seconds.
- (3) When the pour point is very low, a number of freezing mixtures with decreasing lower temperature should be used.
- (4) When the separation of wax crystals starts, great care should be taken



not to disturb the mass of the oil. Even the thermometer should not move in the oil. Any disturbance will delay solidification and so lower results will be obtained.

### Exercises

97. List a few commonly used freezing mixtures along with the pour point that can be determined with their help.
98. What is meant by 'Solid Point' of an oil?
99. What is the difference between 'Wax pour point' and 'Viscosity pour point'?
100. How can the pour point of an oil be lowered?
101. What are pour point depressants?
102. What is 'paraflow'?

### 4.4 Flash and Fire Points

Flash point is the temperature to which a combustible liquid must be heated to give off sufficient vapours to form momentarily a flammable mixture with air when a small flame (of standard dimensions) is brought near the surface of the liquid under specified conditions.

It is therefore the minimum temperature at which, provided other conditions are satisfied, only a momentary flash is produced. The flash immediately disappears for want of more vapours, i.e., the temperature is not high enough for the vapours to be formed at sufficiently high rate.

At a slightly higher temperature, the heat from the flash becomes sufficient to evaporate more liquid and maintain combustion. This minimum temperature (usually 5 to 40°C higher than Flash Point) at which an oil gives off sufficient vapour which when ignited continues to burn for at least 5 seconds is known as FIRE POINT of the oil.

A fire may develop if a set of the following three conditions (known as FIRE TRIANGLE) is simultaneously satisfied:

- (a) A source of ignition (Ignition sources are abundant—anything from static electricity, flame, an arc, a single spark, a cigarette, a match to ash from a pipe, and many more)
- (b) Oxygen (abundantly present in air)
- (c) Combustible vapours within the Explosive Range—a combustible vapour does not burn even when ignited in presence of air ( $O_2$ ) if its concentration in the vapour-air mixture is (i) less than this range ('too lean') or (ii) more than this range ('too rich').

[This latter fact is utilised in making hydrocarbon mixtures less flammable (for use as Industrial Cleaners) by the addition of (i) a non-combustible liquid such as  $CCl_4$  (not widely used because of high toxicity), or (ii) less-combustible chlorinated substances such as trichloroethylene and methylchloroform, as they bring down the concentration of the combustible vapour below the explosive range and make them 'too lean' to ignite.]

Flammable liquids are volatile and speed of evaporation (Evaporation



Rate) increases appreciably when the liquid is heated. The vapours being heavier than air, go on accumulating at the lowest level, such as pits under the tanks, where their concentration reaches within the explosive range and explode and burn in the presence of an ignition source. This can be prevented by mechanical ventilation of any pits at the bottom of oil tanks—this increases the rate of diffusion of vapours and the explosive range is not approached.

### *Significance*

Though unrelated to the lubricating property of the oils, a knowledge of Flash and Fire Point is helpful in providing safeguards against fire hazards during their storage, transportation, handling and use. Their practical importance for transformer oils is obvious. They are also of immense importance for illuminating oils—to ensure safety, flash point of illuminating oils (e.g., kerosene) should be reasonably above the average maximum atmospheric temperature of a country.

Although flash point and fire point are not sufficient as the sole indices of a fire hazard, they have been used for comparative ratings of the fire hazard potential of different flammable liquids and for labelling their containers accordingly—liquids having flash points less than 140° F are called **FLAMMABLE LIQUIDS** and those with flash points above 140° F are called **COMBUSTIBLE LIQUIDS**.

Fire-insurance companies are concerned about the flash points of the oils stocked by their Policy Holders. Also, Railways are normally concerned about the flash points of the oils they carry.

The volatility of a liquid markedly increases when it is heated to or above its flash point. So, a low flash point indicates appreciable evaporation losses and possibility of formation of gas-locks in fuel pipes of SPARK Ignition Engines.

Flash and Fire-points have also been used to detect solvent contamination and to determine the approximate extent of dilution of the Lubricating oils.

Flash point is higher for oils of paraffin base than those of naphthenic base. This test is therefore a rough guide as to the base of an oil.

The test is also useful to refiners in controlling the manufacturing process.

#### *4.4.1 Determination of Flash Point by Abel's Flash Point Apparatus*

The cylindrical oil cup (made of brass) and the lid (also made of brass and provided with a paddle stirrer, an opening for a thermometer, an arrangement for applying a small test flame and three small openings—one for the application of test flame and the other two for the entry for air into the oil cup—covered by a sliding shutter) are thoroughly cleaned and dried. The cup is filled with the oil sample to a level such that the tip of the metallic pointer fixed on the side of the cup just dips in the oil. The lid is tightly fixed on the cup, the thermometer is inserted and the shutter is closed. The cup is now supported by its flange over a copper air-jacket which is enclosed by a cylindrical vessel made of copper (Figure 6). Through a funnel, the



outer vessel is filled with warm water at 130°F (for oils having flash point up to 90°F) or with cold water (for oils flashing from 90°F to 120°F) which is heated electrically. The test flame is lighted and adjusted to the size of a white bead mounted on the cover. The sample is heated at a rate of 5°F per minute and the stirring paddle is turned at a speed of approximately one revolution per second. When the temperature of the oil reaches within 15°F of the probable flash point, first application of the test flame is made by pulling the sliding shutter outwards when the test flame drips into the central opening in the lid and comes in contact with the ascending vapour-air mixture. Subsequently, the test flame is applied at every 2°F rise of temperature. When the application of the test flame first produces a distinct blue flash in the interior of the oil cup, the temperature on the test thermometer is recorded (let it be  $t_1^\circ\text{F}$ ) and heating is discontinued. The temperature of the oil continues to rise for some time. The oil is then allowed to cool down (if the cooling rate is too slow, some cold water may be added to the bath through the funnel). When the temperature comes down to within 10°F of  $t_1$ , test flame is again applied at every 2°F fall of temperature. The lowest temperature at which flash is produced is recorded. Let it be  $t_2^\circ\text{F}$ . The flash point of the oil sample is given by

$$= \frac{(t_1 + t_2)}{2} ^\circ\text{F}. \quad (4.12)$$




Fig. 6 Abel's flash point apparatus

- |                                  |                                  |
|----------------------------------|----------------------------------|
| A—Tripod stand                   | B—Copper air jacket              |
| C—Heating coil                   | D—Water inlet                    |
| E—Water outlet                   | F—Air gap                        |
| G—Brass oil cup<br>(with flange) | H—Stirrer                        |
| J—Lid                            | I—Pointer                        |
| L—Test flame                     | K—Sliding shutter                |
| T <sub>1</sub> —Test thermometer | M—White bead                     |
| N—Water bath                     | T <sub>2</sub> —Bath thermometer |



### Precautions

- (1) As moisture affects the flash point, all parts of the cup and its accessories should be dried before placing oil in the cup.
- (2) No oil should remain between the sliding and fixed plates forming the cover of the cup. If necessary, these should be separated and cleaned. Care should also be taken to prevent wetting of the cup above the pointer tip.
- (3) With very low flashing oils, the sample (sometimes the oil cup itself) may be cooled in melting ice before filling.
- (4) Always a fresh portion of the oil sample should be used. A second determination on the same portion of the oil shows a higher flash point.
- (5) The thermometer bulb should dip into the oil.
- (6) For applying the test flame, the slide should be drawn open slowly and closed quickly.
- (7) Stirring should be discontinued during the application of the test flame.

### Exercises

103. What is the purpose of the air jacket surrounding the oil cup?
104. What is Spontaneous Ignition Temperature (S.I.T.) of a liquid?
105. What are the factors that affect the flash and fire points of oils?
106. How does the presence of water affect the flash point of an oil?
107. How is free water removed from an oil?
108. What is meant by a 'Freaky' flash?
109. Why fatty oils do not have sharp or distinct flash points?
110. What is meant by Flash Point 'Closed' and Flash Point 'Open'? Which one is reproducible and why?
111. Describe the main difference between the Abel's closed-cup and Pensky-Marten's closed-cup methods for flash point determination.

## 4.5 Aniline Point

Since like dissolve like, aniline is readily soluble in those lubricants which are rich in aromatic and naphthenic compounds (all containing ring structures). In lubricants richer in paraffins, dissolution takes place at higher temperatures. The tendency of a lubricant to mix with aniline is expressed in terms of Aniline Point of the sample.

Aniline Point (also known as Standard Aniline Point), with respect to petroleum oils, is the lowest temperature at which the oil is completely miscible with an equal volume of freshly distilled aniline. Alternatively, Aniline Point is the minimum equilibrium solution temperature for equal volumes of aniline and the lubricant sample.

### Significance

Aniline point of any lubricant is a measure of its aromatic content. A lubricant with a low aniline point (therefore having high aromatic content) will tend to attack (solvate and swell) the rubber seals, used in the system to prevent leakage. The sensitivity of a rubber to a lubricating oil depends on



the characteristics of the rubber formulation (composition), and for a rubber seal of fixed composition, the severity of attack increases with decrease in Aniline Point.

The best way to ascertain the probable action of a lubricating oil on rubber is, of course, to immerse the particular rubber in the oil and observe any swelling or softening; but this is a time consuming exercise and may involve weeks or months. The aniline point of an oil, which can be experimentally measured within hours, therefore, can be used as advance information as to the possible deterioration of rubber sealing, gasket and packing material in the presence of the oil.

A lubricant of high aniline point is recommended for systems in which rubber seals are being used. Also the lubricants of almost the same aniline points should be used in a system, as any variation may change the volume of rubber seals and leakage might take place.

#### *Mixed Aniline Point*

There may be certain lubricants (with very high aromatic content) which when mixed with equal volume of aniline may remain completely miscible and separation into different phases may not be observed even at the time of solidification. For determining such low aniline points, 1 volume of sample is mixed with 2 volumes of aniline and 1 volume of a suitable diluent (n-hexane or n-heptane). Addition of the diluent lowers the miscibility of aniline with the sample and so with decrease in temperature, separation of phases can be easily observed. The equilibrium solution temperature observed under these conditions is known as Mixed Aniline Point, which can be used in the same way as the Standard Aniline Point.

#### *4.5.1 Determination of Aniline Point of an Oil*

Equal volumes of the sample and aniline are heated to effect complete dissolution and then cooled under controlled conditions. The temperature at which the two phases separate, as indicated by the sudden appearance of cloudiness throughout the medium, is reported as aniline point of the sample.

#### *Procedure*

The whole apparatus is cleaned and dried at 100-110°C. 5-10 ml of pure aniline (dried over KOH pellets, filtered and distilled afresh) and an exactly equal volume of the sample (dried by shaking with anhydrous  $\text{Na}_2\text{SO}_4$  and filtered) are transferred to a test tube ( $2.5 \times 15$  cm) made of heat resistant glass. The tube is fitted with a cork, holding an electrically operated wire or glass rod stirrer and a thermometer (Aniline-Point Thermometer of appropriate range) with its bulb about 5 mm above the bottom of the tube. The tube is inserted into an outer air jacket ( $4 \times 17.5$  cm) also made of heat resistant glass (Figure 7). The aniline & sample mixture is stirred to get a homogeneous solution. If miscibility is not complete at room temperature, the jacket (holding the tube) is immersed in a hot bath. Stirring is continued and the temperature of the bath is raised until the solution is complete. The jacket is



then withdrawn from the hot bath and, while stirring gently, the temperature is allowed to fall at a rate below  $1^{\circ}\text{C}$  per minute (a cold bath may be used, if necessary). The temperature at which the outline of the thermometer bulb is obscured, due to cloudiness or haziness in the solution, is reported as the aniline point of the sample. This is  $1\text{--}2^{\circ}\text{C}$  below the temperature at which the turbidity is first observed.




Fig. 7 Aniline point apparatus.

- |   |                                |
|---|--------------------------------|
| A—Outer air jacket                        | B—Test tube                    |
| C—Air gap                                 | D—Corks                        |
| E—Equal volumes of oil and aniline        | F—Glass stirrer with auger tip |
| G—Rubber tubing                           | H—Variable speed motor         |
| T <sub>1</sub> —Aniline point thermometer |                                |

### Precautions

- (1) The whole apparatus and all the reagents must be perfectly dry as the presence of even traces of moisture gives erroneous high results.
- (2) Aniline being hygroscopic, water should not be used even in hot and cold baths. Instead a nonaqueous, non-volatile, transparent liquid should be used.
- (3) In case the expected aniline point is below the dew point of the atmosphere, the space above the aniline-sample mixture in the tube should be filled with dry  $\text{N}_2$ .
- (4) Aniline being highly toxic, it should not be sucked into the pipet by mouth. A pipet provided with a rubber suction bulb or an aspirator should be used.
- (5) Stirring should be done at such a rate as to avoid any splashing of the liquid or formation of air bubbles.



**Exercises**

112. What is the purpose of the air jacket enclosing the test tube?
113. What is the effect of the viscosity of mineral oil on its action on rubber?
114. What is the relation between the aromatic content of a lubricating oil and its Aniline Point?
115. Which type of oils have the highest aniline points?
116. What are the ranges of aniline-point thermometers?
117. How is aniline point related to the ignition quality of a diesel fuel?

**4.6 Neutralisation Number****Definitions**

1. Total Acidity, Acid Number or Acid Value of a lubricating oil is the amount of titrating base, expressed as mg of KOH, required to neutralize all acidic constituents of 1 g of the sample.
2. [Total] Basicity, Base Value (Alkali Value) or Base Number (Alkali Number) of a lubricating oil is the amount of titrating acid, expressed as mg of equivalent KOH, required to neutralize all the basic constituents of one gram of the sample.
3. Inorganic Acidity, Strong Acid Number or Strong Acid Value represents the mg of KOH used to neutralize the mineral acid content of 1 g of the sample. The difference of Total Acidity and Inorganic Acidity is equal to Organic Acidity.
4. Strong Base Number or Value is the amount of acid, expressed as mg of equivalent KOH, used to neutralise the strong basic constituents of 1 g of sample.

The terms Neutralisation Number or Neutralisation Value may be used to represent any of the values.

**Sources of Acidity & Significance**

Fatty oils consist mostly of glyceryl or other esters of higher fatty acids—in some cases, notable amounts of free acids themselves are present. The amount of the free acid present depends on the source from which the oil is taken. The acid content or value of fatty oils increases with time due to hydrolysis with moisture and is therefore a rough indicator of the age of the oil, i.e., it gives an idea of how old a fatty oil is. The deterioration in the flavour of the edible oils with time is due to the increase in the free acid concentration formed by hydrolysis and oxidation.

The presence of free mineral acids in lubricating oils is very rare and is a pointer to external contamination.

New, unblended petroleum oils should have very low neutralisation values usually ranging from 0.02 to 0.1. Values higher than this indicate faulty refining, i.e., acids and bases used during the refining process have not been completely removed. Blended or compounded oils may have higher values of



neutralisation number because of the presence of additives such as oiliness carriers (fatty acids, fatty oils), oxidation and corrosion inhibitors (phenols, aniline), etc. The test is therefore used to maintain specification control on new lots of the lubricant.

As the oil is used, the neutralisation number may increase due to contamination (e.g.,  $\text{SO}_2$  from the combustion of S in the fuel,  $\text{CO}_2$  from combustion or that present in atmosphere) and/or oxidation of the oil. The oxidation of the oil results in the formation of oil soluble alcohols, ketones, acids and peroxides (which may polymerise to give insoluble resins) thereby increasing the acid number, viscosity and darkening the oil colour. The rate and extent of oxidation of the oil during use depends on temperature, length of exposure to air or oxygen, amount of moisture, catalysts present (formed by the action of oxidation products on the metal surface), type of oil and the inhibitors used.

Periodic determination of Acid Number, therefore, can be used to indicate the progress of oxidation of the lubricant and for systems operating consistently under exactly the same conditions without external contamination, a record of such determinations is helpful in deciding the stage, with a considerable degree of accuracy, where the lubricant needs replacement.

Although the neutralisation number gives the amount of acid or base present in the lubricating oil, it gives no information about their source and corrosive nature.

#### 4.6.1 Determination of Total Acid Value of an Oil

##### *Reagents Required*

1. Standard alcoholic potassium hydroxide solution (N/100)
2. A suitable titration solvent (p. 8)
3. Phenolphthalein indicator solution
4. p-Naphtholbenzoin indicator solution.

##### *Theory*

A known weight of the oil sample is dissolved in a suitable solvent and titrated with a standard alcoholic solution of KOH to a definite end-point.



##### *Procedure*

Weigh accurately the beaker containing the oil sample and a dropper. Transfer 150 drops (about 5 g) of the oil to a titration flask and take the final weight of the beaker, oil and dropper. The difference gives the weight of the oil sample. Add with a measuring cylinder 100 ml of a suitable titration solvent. [Select, from 1 to 6 (p. 8), a solvent that completely dissolves the sample]. Shake vigorously to dissolve the oil (in case of alcohol as solvent, heat the reaction mixture to boiling on a water bath). Add 20-25



drops of p-naphtholbenzoin solution or 10-12 drops of phenolphthalein indicator and titrate against N/100 alcoholic KOH solution until a sharp colour change from orange to green or bluish green (in case of p-naphtholbenzoin indicator) or until disappearance of pink colour (in case of phenolphthalein indicator). Record the volume of alkali used as A ml. Run a blank on the reagents used and record the volume of alkali consumed as B ml.

#### 4.6.2 Determination of Strong Acid Number or Inorganic acidity of an Oil

##### Reagents Required

1. Standard potassium hydroxide solution (N/100)
2. Methyl orange indicator solution.

##### Procedure

Transfer 25-50 g of accurately weighed oil sample to a 500-ml separating funnel. Add 100-150 ml hot distilled water, shake vigorously and allow to stand for the separation of oil and water layers. Drain the water layer into a 500-ml conical flask. Wash the oil layer with two to three 50-ml fractions of hot distilled water and collect the washings in the same conical flask. Add 3-4 drops of methyl orange indicator and titrate against N/100 KOH solution until the colour changes from red to yellow. Record the volume of alkali used as A ml. Run a blank on the same volume of hot water and record the volume of alkali used as B ml.

##### Observations & Calculations

Initial weight of beaker, oil and dropper =  $W_1$  g

Final weight of beaker, oil and dropper =  $W_2$  g

Weight of oil sample taken =  $(W_1 - W_2)$  g

Volume of N/100 KOH used in the test = A ml

Volume of N/100 KOH used in the blank = B ml

Therefore volume of N/100 KOH used against acid in  $(W_1 - W_2)$  g of oil =  $(A - B)$  ml

Acid value =  $\frac{\text{ml of KOH used} \times \text{Normality} \times 56}{\text{weight of sample}}$   
(or strong acid value, as the case may be)

$$= \frac{(A - B)}{(W_1 - W_2)} \times \frac{1}{100} \times 56$$

$$= \frac{(A - B)}{(W_1 - W_2)} \times 0.56$$

##### Precautions

1. The solvent used should be freshly distilled.



2. The alcoholic solution of KOH must be standardised just before the test.
3. While carrying out the test on 'Fatty Oils' the reaction mixture should not be heated.
4. In case the pink colour fades repeatedly after subsequent additions of alkali, the titration should be completed rapidly and the first appearance of pink colour should be taken as the end-point.
5. Phenolphthalein is a satisfactory indicator for pale oils but when the test sample is highly coloured (red or black) a smaller weight of the sample should be taken and p-naphtholbenzoin indicator should be used or better the end-point should be determined potentiometrically.

### Exercises

118. When phenolphthalein is used as indicator, the pink colour at the end-point sometimes fades away after a few seconds. What is the possible cause of this?
119. In determining the acid value of 'fatty oils', what will happen if the reaction mixture is heated?
120. What inference is drawn if addition of p-naphtholbenzoin indicator to the oil sample, dissolved in a suitable solvent, produces a green or bluish green colour? How is the titration performed?

### 4.7 Saponification Value or Number or Koettsdoerfer Number

Saponification is the hydrolysis of an ester with NaOH or KOH to give alcohol and sodium or potassium salt of the acid. The term originated from the alkaline hydrolysis of fatty oils which led to formation of soaps.

*Saponification Number or Value* of an oil is the number of mg of KOH required to saponify fatty material present in 1 g of the oil.

Mineral oils, being mixtures of hydrocarbons, do not react with KOH and so are not saponifiable. Vegetable and animal oils, however, are mixtures of glyceryl esters of fatty acids and so require large amounts of alkali to get hydrolysed. Their saponification values are consequently very high and each fatty oil has its own characteristic value.

### Significance

The measurement of saponification value, in the absence of impurities that can react with alkali (such as inorganic or organic acids), can be used

- (a) to distinguish between fatty oils and mineral oils.
- (b) to identify a given fatty oil (for fatty oils, saponification value is a measure of molecular weight).
- (c) to determine, approximately, the extent of adulteration (if any) in a given oil.
- (d) to determine the extent of compounding (fats and oils added to



improve oiliness) in a lubricant. When the type of fatty ingredient in a compounded oil is known, its exact amount is given by

$$\text{Percentage of fatty oil} = \frac{C}{F} \times 100$$

where C = saponification value of the compounded oil (or lubricant)

F = saponification value of the fatty oil

Though increases in saponification values of lubricants during use are of the same order as those in acid values, they have not been correlated to the extent of deterioration of the oil.


#### 4.7.1 Determination of Saponification Value of an Oil

##### Reagents Required

1. Standard hydrochloric acid (N/2)
2. Alcoholic potassium hydroxide solution (N/2)
3. Ethyl alcohol or Ethyl methyl ketone
4. Phenolphthalein indicator solution.

##### Theory

A known weight of the sample is mixed with a known excess of standard alcoholic KOH solution and refluxed.



(where R, R' and R'' are alkyl groups) Potassium salts of fatty acids (soaps)

The unreacted KOH is titrated back with standard acid using phenolphthalein as indicator.



##### Procedure

Transfer about 5 g of accurately weighed oil sample to a 500-ml alkali-resistant conical flask. Add 50 ml of N/2 alcoholic KOH and 50 ml of alcohol or ethyl methyl ketone (to act as a solvent) through a pipet. Add the same amounts of the solvent and N/2 alcoholic KOH to another flask for Blank determination. Fit the two flasks with air condensers (a long narrow glass tube) and reflux the contents on a water bath for a minimum period of 1 hour. Cool the contents slightly, disconnect the condenser and rinse it with a small amount of distilled water into the flask. Add 10-12 drops of phenolphthalein indicator and titrate the contents of two flasks with a standard solution of HCl (N/2) until the pink colour has just disappeared.



*Observations and Calculations*

Weight of the sample taken =  $W$  g

Volume of alcoholic KOH added to both the flasks = 50 ml

Volume of solvent added to both the flasks = 50 ml

Volume of  $N/2$  HCl used in the sample determination =  $A$  ml

Volume of  $N/2$  HCl used in the Blank determination =  $B$  ml

Then the volume of  $N/2$  HCl equivalent to KOH used in saponifying  $W$  g of the sample =  $(B-A)$  ml

mg of KOH present in  $(B-A)$  ml of  $N/2$  KOH =  $(B-A) \times \frac{1}{2} \times 56$


Saponification value of the sample =  $\frac{(B-A)}{W} \times 28$

*Precautions*

1. If the room temperature is appreciably high (as in summer months) and there is a possibility of loss of vapour to the atmosphere, the air condenser should be replaced with a water condenser and boiling should be done at a slow rate.
2. To hasten the process of saponification, the sample flask should be occasionally shaken during the reflux operation.
3. Ethyl methyl ketone as a solvent should be preferred as it raises the boiling point and thus hastens saponification.

**4.8 Iodine Value**

Oils and fats, both animal and vegetable, are mixtures of mixed glycerides represented by the general formula



and are formed from glycerol and monobasic acids. The acids present in combination with glycerol have all even number of carbon atoms ( $C_4$  to  $C_{22}$ ) and may be saturated and/or unsaturated. Commonly occurring acids are:

Acid	Important source
1. $C_{15}H_{31}COOH$ palmitic acid	Butter, palm oil
2. $C_{17}H_{35}COOH$ Stearic acid	Fats
3. $CH_3.(CH_2)_7.CH=CH.(CH_2)_7.COOH$ Oleic acid	Olive oil, palm oil, peanut oil, soyabean oil
4. $CH_3.(CH_2)_4.CH=CH.CH_2.$ $CH=CH.(CH_2)_7.COOH$ Linoleic acid	Cottonseed oil, linseed oil, soyabean oil, corn oil



5.  $\text{CH}_3. \text{CH}_2. \text{CH}=\text{CH}. \text{CH}_2. \text{CH}=\text{CH}.$   
 $\text{CH}_2\text{CH}=\text{CH} (\text{CH}_2)_7. \text{COOH}$   
 Linolenic acid Linseed oil
6.  $\text{CH}_3. (\text{CH}_2)_3. \text{CH}=\text{CH}. \text{CH}=\text{CH}. \text{CH}=\text{CH}.$   
 $(\text{CH}_2)_4. \text{CO}. (\text{CH}_2)_2 \text{COOH}$   
 Eleostearic acid Tung oil

The combinations having a predominance of short-chain saturated fatty acids or long chain fatty acids with a considerable degree of unsaturation are liquids at ordinary temperatures and are called oils; while others, that are solids at ordinary temperatures, are known as fats.

The degree of unsaturation of oils and fats is reported in terms of their Iodine Number or Iodine Value (I.V.) which is the number of grams of Iodine equivalent to the amount of Iodine Monochloride (ICl) absorbed by 100 g of the oil.


### Significance

Each oil has its own characteristic iodine value (varying between narrow limits), and so the determination of iodine value can be utilised to detect and even to determine (though approximately) the extent of contamination in any specific oil.

Iodine values have been used to classify oils into

- (i) Drying oils—Linseed oil, tung oil, perilla oil, etc., having iodine values (I.V.)  $> 150$
- (ii) Semi-drying oils—Soyabean oil, dehydrated castor oil, etc., with iodine values between 100 and 150
- (iii) Non-drying oils—Castor oil, coconut oil, olive oil, etc., with iodine values  $< 100$ .

Unsaturation confers drying characteristics on oils—when a thin layer of an oil with a high degree of unsaturation is spread on a smooth surface and exposed to air and light, it takes up oxygen at the double bond sites, and gets oxidised and polymerised [through the intermediate formation of peroxides,



into a hard, coherent, tough, infusible, cross-linked, resin-like film. The rate of drying and the nature of the film formed depends (in addition to other factors like temperature, presence of driers, etc.) on the degree of unsaturation or I.V. of the oil used.



Thus an oil of high I.V. is most suitable for the manufacture of paints and varnishes but for an oil to be used as a lubricant, its I.V. should be as low as possible so that during use it is not deteriorated to any appreciable extent due to oxidation and polymerisation.


#### 4.8.1 Determination of Iodine Value of an Oil

##### Reagents Required

1. Standard sodium thiosulphate solution (N/10)
2. Wij's solution
3. Potassium iodide solution (10%)
4. Carbon tetrachloride or chloroform
5. Freshly prepared starch solution.

##### Theory


A known weight of the oil is dissolved in  $\text{CCl}_4$  or  $\text{CHCl}_3$  and treated with a known excess of Wij's solution (solution of  $\text{ICl}$  in glacial acetic acid). One molecule of  $\text{ICl}$  adds on each double bond:



After the reaction is complete,  $\text{KI}$  solution is added which is oxidised to  $\text{I}_2$  by the unreacted  $\text{ICl}$ :



The liberated iodine is titrated with standard  $\text{Na}_2\text{S}_2\text{O}_3$  solution using starch solution as indicator near the end-point:



From the amount of iodine (in the form of  $\text{ICl}$ ) added and that left unconsumed, as measured iodometrically, the iodine value of the sample can be calculated.

##### Procedure

Transfer 25 ml of  $\text{CCl}_4$  and 25 ml of Wij's solution each to two 500-ml iodine titration flasks. Strain the oil sample through a filter paper to remove all the solid material and moisture present in the sample. Accurately weigh 0.05 - 0.5 g of the sample [weight depending on the I.V. (200-50) of the sample] and transfer to one of the two flasks. Close the flasks with glass stoppers moistened with a little 10%  $\text{KI}$  solution. Swirl the flasks to mix the contents intimately and keep in dark for about 1 hour at a temperature below  $30^\circ\text{C}$ . Add 20 ml of  $\text{KI}$  solution to both the flasks, washing down the stopper, and dilute with about 100 ml of distilled water. Titrate the



liberated iodine with  $N/10$   $Na_2S_2O_3$  solution. When the colour of the solution turns light yellow, add about 1 ml of freshly prepared starch solution and continue the titration until the first disappearance of blue colour. Record the volume of  $N/10$   $Na_2S_2O_3$  solution used in sample titration as A ml and that in blank titration (without oil) as B ml.

#### Precautions

- (1) Wij's solution should be added with the help of a burette or a vacupet. This solution should never be sucked into the pipet with mouth.
- (2) The sample and the glassware used must be completely dry.
- (3) The amount of the sample taken should be such that the Wij's solution added is about 100% in excess of the expected requirement.
- (4) As far as practicable, the addition of solutions (Wij's solution or KI solution) to the two flasks should be simultaneous.
- (5) During titration, the flasks should be frequently stoppered and shaken vigorously to ensure complete titration of the iodine present in  $CCl_4$  layer.

#### Observations and Calculations

Weight of the oil sample taken = W g

Volume of  $N/10$   $Na_2S_2O_3$  used to titrate excess iodine in sample determination = A ml

Volume of  $N/10$   $Na_2S_2O_3$  used to titrate total iodine in blank titration = B ml

Therefore, volume of  $N/10$   $Na_2S_2O_3$  equivalent to iodine consumed by Wg of the Oil =  $(B-A)$  ml

Iodine present in  $(B-A)$  ml of  $N/10$

$$\text{iodine solution} = (B-A) \times 127 \times \frac{1}{10} \times \frac{1}{10^3} \text{ g}$$

$$\text{Therefore, Iodine value} = \frac{(B-A)}{W} \times 127 \times \frac{1}{10} \times \frac{1}{10^3} \times 10^2$$

$$= \frac{(B-A)}{W} \times 1.27$$

#### Exercises

121. What is the effect of the presence of moisture in the sample, acetic acid or glassware, on the test?
122. Why is the reaction mixture kept in dark?
123. Why is the glass stopper moistened with KI solution?

#### 4.9 Emulsions

Emulsions are dispersions of small droplets of one liquid in another liquid.



neither liquid being soluble in the other. They are electrically stabilised by some type of surface active substances known as emulsifiers. When the amount of the emulsifier is small, the emulsion is relatively unstable ('loose' emulsion) and the dispersed droplets coalesce fairly easily to give large drops ('cracking' of emulsion). When the concentration of the emulsifier is large, the dispersed droplets are finer and the emulsion is hard to break ('tight' or stable emulsion).

Emulsions are used as lubricants for certain specific jobs:

- (a) Oil-in-water (o/w) emulsions are used as coolants in metal working, grinding, boring, turning, cutting, etc., and as lubricants for large diesel-motor pistons.
- (b) Water-in-oil (w/o) emulsions (also called Invert Emulsions) are used mainly as fire-resistant hydraulic fluids and as compressor and pneumatic tool lubricants.

Depending upon the prospective service, the emulsifying tendencies of an oil can be a benefit or a drawback. Emulsification is *advantageous* when an oil is to be used in presence of water, as in case of steam cylinder oils where wet steam is involved and lubrication of the cylinder walls and valve seats is maintained by emulsified oil. Therefore, fatty oils which most readily form stable emulsions with water are added to straight mineral cylinder oils to increase their tendency to emulsify and to stabilize the emulsions formed.

Formation of emulsions in most operations may be *Harmful* as emulsification increases the viscosity and consequently the coefficient of friction. Emulsions have a tendency to collect dirt, grit particles and other foreign matter which may cause abrasion and wearing out of the lubricated parts. Emulsions may form sludges, insulate coolers, clog oil-lines and filters and may even cause corrosion of the metal surface by carrying salts from water through the lubricating system and by developing an e.m.f. between the bearing and the journal. Emulsions are also ideal medium for microbiological growth. Since the emulsion formed must be removed, a considerable amount of oil is lost.

These problems can be minimised by using a lubricant that would not emulsify during use or form only a loose emulsion that readily breaks (Rapid water separation reduces the Resting Time required for lubricating oils). In steam turbines, condensation of steam leads to the formation of water-in-oil emulsion whose Demulsibility (the ability of a lubricant to separate from its emulsion with water) depends on the composition of the oil, the impurities left in the lubricant during refining, on the presence of additives, oxidation products of the lubricant during its use and other foreign contaminants. The tendency to demulsify decreases with the time the lubricant has been in use.

The demulsibility of a lubricant is reported in terms of the time in which an emulsion produced from 40 ml of the sample and 40 ml water (at 130°F; 180°F for lubricants with viscosities more than 450 SUS) cracks (breaks) to give two distinct layers, when left undisturbed. In case of incomplete demulsification at the end of 1 hour, a 3-ml cuff or emulsion is



neglected; if it is more, the volume in ml of the oil, water and emulsion are reported.

Steam Emulsion Number (S.E.N.) determines emulsion characteristics resulting from steam condensing in oil. It is the time in seconds in which oil and water separate in distinct layers from an emulsion (at 200-203° F) produced by bubbling steam into 20 ml of oil until the volume of emulsion becomes 40 ml.

S.E.N. is useful in defining the demulsibility of a new oil. Exceptionally high values during service indicate foreign contamination or malfunctioning of some component.

#### 4.9.1 *Water Emulsion Test*

In the Water Emulsion Test (United States Steel Method), 40 ml of the oil sample are taken in a 100-ml graduated cylinder which is immersed in a constant temperature bath maintained at 130° F or 180° F. 40 ml of distilled water heated to the temperature of the bath are added slowly to the oil so as to complete the addition in one minute. The mixture is then emulsified by stirring for 5 minutes with a paddle rotating at 1500 revolutions per minute. After switching off, the paddle is slowly raised out of the cylinder. Simultaneously, a stop watch is started. The cylinder is then allowed to remain in the bath at the test temperature. At suitable time intervals, the cylinder is taken out only to inspect and is reimmersed in the bath immediately after each reading. The results of the experiment are recorded in the following tabular form:

Time in minutes	1	2	3	4	5	6	7	8	9	10	15	20	30	40	50	60
ml of the oil layer																
ml of the water layer																
ml of cuff or emulsion																
left (intermediate layer)																

#### *Precautions*

- (1) The graduated test cylinder should be immersed in the constant temperature bath at least up to 85-ml mark.
- (2) After raising the paddle out of the cylinder, it should be held in that position so as to allow as much of emulsion as possible to return to the cylinder.

#### 4.9.2 *Steam Emulsion Number*

In the ASTM Test, 20 ml of the oil to be tested is taken in the standard graduated test tube (A) which is suspended in a beaker containing water (B-Emulsifying bath) at an initial temperature of about 70° F. Steam from the generator (C) is passed through a delivery tube (D) into the oil (Figure 8). The steam jet violently agitates the oil which becomes intimately mixed with water (formed by the condensation of steam) and an emulsion is formed. The latent heat of condensation of steam raises the temperature of the emulsion. Steam is admitted at such a rate (adjusted with the help of pinch



cock  $E_3$ ) as to raise the temperature of the emulsion to about  $190^{\circ}\text{F}$  in about 1 minute. Steaming is continued till the volume of emulsion in the test tube becomes  $40 \pm 3$  ml. At this stage, the delivery tube and the thermometer along with the cork are quickly withdrawn from the test tube which is rapidly transferred to the other beaker containing water (F-separating bath), maintained at a temperature of  $200\text{--}203^{\circ}\text{F}$  by bubbling steam from the generator. Immediately as the delivery tube is withdrawn, a stop watch is started to measure the time. The observations are recorded in the tabular form (as in Water Emulsion Test 4.9.1). The time in which the emulsion breaks is reported as Steam Emulsion Number of the oil.




Fig. 8 Steam emulsion number apparatus.

- |                                    |                                     |
|------------------------------------|-------------------------------------|
| A—Graduated test tube              | B—Emulsifying bath                  |
| C—Steam generator                  | D—Delivery tube                     |
| $E_1$ , $E_2$ & $E_3$ —Pinch cocks | F—Separating bath                   |
| G—Burner                           | H—Tripod stand                      |
| I—Clamp stand                      | $T_1$ , $T_2$ & $T_3$ —Thermometers |

#### Precautions

- (1) Before immersing the steam delivery tube into the test tube, steam should be passed through the delivery tube until condensation in the tube ceases.
- (2) The steaming rate should be so adjusted as to double the volume of the contents of the tube in 4–6 minutes.
- (3) The end of the delivery tube dipping into the oil should be cut at an acute angle and should rest at the bottom of the test tube so that no portion of the oil escapes agitation.
- (4) A narrow vertical groove should be made in the side of the cork to permit the uncondensed steam to escape.

**Note:**— The importance of these static tests in industry has considerably decreased. They have been replaced with a Dynamic Demulsibility Test which measures the ability of an oil to separate from water under actual circulating conditions and correlates better with practice.



**Exercises**

124. Name some specific lubricants which must have high water separation tendency, i.e., low S.E.N.
125. What steps should be taken in order that a lubricant may possess good demulsifying characteristics?
126. What are 'Soluble Oils'?
127. What are defoamants? Give some examples.

**4.10 Greases**

A grease is essentially a semi-solid to solid combination of a thickening or gelling agent (soap or a mixture of soaps) and a liquid lubricant (petroleum oil, fatty oil or synthetic oil). It may also contain other ingredients which are added to impart special characteristics.

Whereas oils move of their own accord, pressure has to be applied to greases to make them flow. Thus greases give a higher coefficient of friction than lubricating oils; yet they are preferred to oils under the following conditions:

- (1) Where the oil is squeezed out due to heavier loads, low speeds, or does not remain in place due to intermittent operation or sudden jerks.
- (2) Where the design of the machine is such that the parts to be lubricated can in no way retain the liquid lubricant, e.g., open gears.
- (3) Where the lubricant is also required to act as a seal against the entrance of dirt or moisture.
- (4) Where dripping or splashing of oils cannot be tolerated, e.g., machines preparing edible articles, paper, textile, etc.
- (5) Where an oil is seldom added, e.g., electric motor bearings.
- (6) Where frequent lubrication is either inconvenient or uneconomical (automobile wheel bearings.)

**4.10.1 Consistency or Mechanical Stability**

Some greases, which on being in service, retain their original hardness or softness for a long duration are said to be more consistent than those which more readily lose their hardness on being worked. Consistency, as applied to a lubricating grease, is thus its ability to resist a change in its stability or degree of stiffness likely to be produced by an operating mechanical shear (whether in laboratory or in service). Consistency is thus a characteristic of plasticity (as viscosity is of fluidity) and represents the ability of a grease to resist deformation under the application of force.

***Penetration Number, Value, Index or Yield Value***

Penetration number with respect to a lubricating grease is the depth (in tenths of an mm) that a cone of standard dimensions penetrates vertically into the sample under test, under prescribed conditions of weight (150 g), temperature (25° C) and time (5 seconds.)



*Significance of Penetration Test*

Penetration value of a grease is a measure of its degree of stiffness (i.e., whether it is hard or soft). The hardness or stiffness of a grease may vary from that of a heavy viscous liquid to that of a stiff solid mass (e.g., a cake of soap). The lower the penetration value, the harder the grease—which means pumping of grease is difficult and coefficient of friction is more. However, the grease can better withstand higher loads at lower speeds. A higher penetration number means a softer grease, lower resistance to flow, increased pumpability but unable to withstand higher loads and more attention will have to be paid to prevent leakage.

Measurement of penetration member of 'unworked' (as marketed—a grease that has received only the minimum handling in transfer from sample-can to test-apparatus and which has not been subjected to the action of a grease worker) and 'worked' (subjected to standard shear rate with a manual or mechanically-operated worker) samples can be utilised to assess the consistency of a grease, and also to study its gel-fluid reversibility (thixotropic nature). It is also used as a control test for product uniformity and serves as a basis for dividing greases into different grades.

*4.10.2 Determination of Penetration Number of a Grease**Procedure*

Using a corrosion-resistant steel spatula, the sample is packed into the grease cup taking care to exclude all air. The cup is then placed in a bath maintained at 25°C for about one hour. The surface of the grease is then smoothened and brought at level with the edge of the cup by scraping off excess of grease with the blade of the spatula.

The grease cup is now placed on the levelled table of the heavy base of the penetrometer (Figure.9) The standard cone (made of brass and fitted with detachable hardened-steel tip) is cleaned and fixed to the holder shaft. The holder is then slowly and very carefully lowered so that the cone tip just touches the grease surface. The dial rod is now pressed down so that it comes into contact with the holder shaft, fixed vertically below, and the reading of the indicator on the circular dial is recorded. By pressing the push button, the shaft is released and the cone falls without measurable friction. Simultaneously, a stop watch is started. The cone is allowed to penetrate into the grease for exactly 5 seconds and then the push button is released. The dial rod is now pressed down until it is stopped by holder shaft, and the indicator reading on the circular dial is again recorded. The difference in the two readings directly gives the distance, in tenths of an mm, through which the cone has penetrated into the grease. The test is repeated 2 to 3 times and the average is reported as the penetration number of the grease.

*Precautions*

- (1) For perfect positioning of the cone in contact with the grease surface, a mirror should be used to remove parallax.






Fig. 9 Penetrometer.

- |                      |                       |
|----------------------|-----------------------|
| A—Levelling screw    | B—Heavy base          |
| C—Table              | D—Spirit level        |
| E—Grease cup         | F—Standard brass cone |
| G—Hardened—steel tip | H—Holder              |
| I—Shaft              | J—Push button         |
| K—Dial rod           | L—indicator           |
| M—Circular dial      |                       |

- (2) As far as possible, all air voids in the sample should be eliminated.
- (3) On pressing the push button, the cone must have a free fall, i.e., the shaft should move in the holder without any measurable friction.
- (4) Before taking subsequent readings, the cone should be wiped perfectly clean and the surface of grease should be smoothened.

### Exercises

128. How does the presence of air voids in the sample affect penetration number?
129. What will be the effect if the movement of holder shaft is not frictionless?
130. Enumerate the important factors on which penetration number of a grease depends.



### 4.10.3 *Dropping Point*

Greases, like emulsions, contain stable colloidal dispersions, but when thickener used is a soap (soap-based greases), the particles are not spherical but crystallites of fibrous shape which result from polymerisation or linear aggregation of soap micelles (colloidal soap molecules). The fibres get tangled and a three-dimensional interconnected structure results. The oil particles get physically entrapped in the interstices of the tangled structure and/or adsorbed on the fibres.

When the temperature of a grease is raised, the interconnected structure ceases to exist; the soap is said to have dissolved in the oil, resulting in the liquification of the grease. Greases, however, do not have any well-defined melting points. The liquification process is therefore more appropriately called the softening of a grease. The softening characteristics of different greases are compared in terms of their Dropping Points. The Dropping Point of a grease is the lowest temperature at which the grease, when heated under specified conditions, becomes sufficiently fluid so that a drop will fall from a cup having a hole of specified dimensions.

The dropping point is a qualitative indicator of heat resistance or thermal stability of a grease, which depends on the nature of the soap and the fatty oil present and, to some extent, on the viscosity of the mineral oil (added to adjust the consistency of the grease). Lime soap greases generally have lower dropping points than greases of sodium, lithium or mixed base. The dropping point of some greases, particularly those of aluminium soaps, appreciably decreases upon ageing. Greases containing saturated fatty acids have higher thermal stability. The dropping point can be increased by adding non-soap thickeners such as carbon black, bentonite, colloidal silica, etc.

### *Significance*

Dropping point provides a practical limit of temperature above which a grease cannot be used as a lubricant in the semi-solid state. The test is useful as a means of identifying greases. In the manufacture of greases, periodic determination of dropping point is used to ascertain the uniformity of the finished product.

### 4.10.4 *Determination of Dropping Point of a Grease*

#### *Procedure*

A chromium-plated brass cup, with an opening of standard dimensions at its bottom, is taken and its larger opening is pressed into sample grease until the cup is filled and a small amount of grease extrudes out of the smaller opening. Excess of grease is removed with a spatula. A wedge of grease, shaped into an inverted cone by revolving the cup against the standard polished metal rod (provided for this purpose along with the apparatus) inserted through the length of the cup, is removed such that only a smooth uniform thin film of grease remains on the walls of the cup.

The cup is now lowered into a pyrex glass test tube with a rim or



indentations near the bottom to support the cup (Figure 10). A thermometer is then inserted through a cork into the tube to such a depth that the tip of the bulb is just above the bottom of the grease cup. The assembly is then lowered into a heating bath (a glass tub containing a transparent oil and fitted with a thermometer and a stirrer). The temperature of the heating bath is then slowly raised (electrically) while the stirrer is working. As the temperature rises, the grease softens and slowly exudes from the orifice of the cup. When a drop of grease gets detached from the bottom of the cup and falls into the tube, the temperatures shown by the two thermometers are recorded. The average of the temperatures is reported as the Dropping Point of the grease sample.




Fig. 10 Dropping point apparatus.

A—Chromium plated brass cup

C—Cork

E—Glass tub

G—Heating coil

T<sub>2</sub>—Bath thermometer

B—Pyrex glass test tube

D—Stirrer

F—Transparent oil

T<sub>1</sub>—Test thermometer



**Precautions**

- (1) The grease film on the walls of the cup should be as thoroughly uniform as possible.
- (2) The thermometer bulb should not touch the grease.
- (3) The bulbs of the test thermometer and bath thermometer should be, as far as possible, at the same level.
- (4) Initial heating may be fast (at a rate of about  $5^{\circ}\text{C}$  per minute) but when the temperature of the bath is about  $15^{\circ}\text{C}$  below the expected dropping point, the heating rate should be so reduced that the two thermometers show a temperature difference of less than  $2^{\circ}\text{C}$ .
- (5) The temperature should be recorded when the grease drop completely separates from the bottom of the cup, i.e., if the drop has a tailing end, it should break completely.


**Exercises**

131. What is meant by bleeding of a Grease?
132. What are Smooth or Fibrous Greases? Give one example of a Fibrous Grease.
133. What is Petrolatum?
134. What is meant by a complex soap?
135. What is the effect of complexing agent on the dropping point of a grease?



## Coal

Coal is a primary fuel, a highly carbonaceous matter formed from fossilised remains of plants [consisting mainly of cellulose  $(C_6H_{10}O_5)_n$  and lignine, a natural plastic binder with approximate formula  $(C_{10}H_{13}O_3)_x$ , with small amounts of resins, fats, waxes and water]. The early stages of transformation (millions of years ago) may have been brought about by the slow action of anaerobic bacteria on vegetable debris from vegetation under water-logged conditions, resulting in the evolution of  $CO_2$  and methane, loss of water; and the acidic and humic substances



formed being absorbed by resistant woody tissue. Further degradation, resulting in loss of water and volatile matter, was possibly brought about by the combined action of heat and pressure—the depth of burial and the time duration governing the extent of transition from Vegetation  $\rightarrow$  Peat  $\rightarrow$  Lignite  $\rightarrow$  Bituminous  $\rightarrow$  Anthracite to Graphite. X-ray studies have shown coals to consist of layers of clustered fused aromatic nuclei stacked one over the other.

The composition of the coals thus varies according to the source and age; so, well defined chemical and physico-chemical properties cannot be expected. For ascertaining the quality and/or ranking of coal, two types of analysis are carried out:

- (i) Proximate analysis
- (ii) Ultimate analysis.

### 5.1 Proximate Analysis

It is the determination of (a) Moisture content (b) Volatile Matter (c) Ash content and (d) Fixed carbon. The analysis is consumer oriented and empirical in nature. The results vary with the procedure adopted and have no absolute significance. However, when the analysis is carried out in accordance with standard specifications (British Standard or American Society for Testing and Materials, ASTM), it gives reproducible results which are essential to assess the suitability of the fuel for a particular domestic or industrial use.



## 5.2 Moisture Content

Moisture which is lost on air-drying is called Surface, Adsorbed or Free Moisture. Amount of free moisture is widely variable and depends on factors like the treatment given to the coal, the extent of subsequent drying, the size of the coal lump, rank of the coal and the nature of its surface. Free moisture is disadvantageous to the extent that

- (i) Water is bought and transported at the fuel price
- (ii) It does not add to the fuel value
- (iii) A considerable amount of heat is wasted in evaporating the moisture during combustion (0.1% loss for every 1 per cent of moisture)
- (iv) Handling of coal may become difficult due to excessive free moisture.

However, coals containing 5 to 10% evenly distributed free moisture have been reported to

- (i) Improve the yield and quality of metallurgical coke formed
- (ii) Produce a more uniform fuel bed
- (iii) Reduce the amount of 'fly ash'.

*Inherent Moisture* is the moisture that is retained by an air-dried coal. It decreases with increasing rank and is a rough indicator of the maturity (age or degree of coalification) of coal. Coals with high inherent moisture are easily oxidised in air and therefore are liable to spontaneous combustion.

### 5.2.1 Determination of Inherent Moisture of a Coal/Coke sample

If the coal/coke sample appears to be wet, spread it on tared pans, weigh and air-dry at room temperature or in the moisture oven at 10 to 15°C above room temperature until the difference in weight between two weighings five hours apart is not more than 0.5%. The loss in weight gives free moisture. Quickly crush and grind the sample, in an air-tight ball mill, to pass through a No. 60 mesh (ASTM). Transfer approximately 1 g of this sample to a porcelain or silica capsule ( $\frac{7}{8}$ " in depth and  $1\frac{3}{4}$ " in diameter) with aluminium cover or a platinum crucible (previously heated, to a temperature at which the sample is to be dried or ignited, and weighed), close with a tightly-fitting cover and weigh. Remove the cover, place the capsule or the crucible in an oven having uniform temperature in all parts and preferably a provision for dry air circulation maintained at a temperature of 105-110°C for exactly 1 hour. Replace the cover, cool in a desiccator and weigh.

#### Precautions

- (1) All the operations after air-drying should be performed quickly to prevent moisture change.
- (2) To prevent oxidation of low-rank coals by air, inherent moisture in their case should be determined in an atmosphere of nitrogen.



*Observations and Calculations*

Let the weight of empty capsule or crucible = A g

Weight of capsule (or crucible) + sample, before drying = B g

Weight of capsule (or crucible) + residue, after drying = C g

$$\text{Inherent Moisture Content} = \frac{B - C}{B - A} \times 100\%$$

The sum of the weight loss on air-drying and inherent moisture gives Total Moisture Content. If a coke sample is dried to constant weight between temperatures 105-200°C, without any preliminary crushing, the loss in weight on percentage bases gives the total moisture content within an error of 0.5%

**5.3 Ash Content**

The useless and non-combustible inorganic matter that is left after burning off the organic matter in coal is known as Ash.

*Free or Extraneous Ash* arises from

- (i) Ankerites and cleats (usually composed of  $\text{CaCO}_3$  &  $\text{FeCO}_3$  along with some  $\text{MgCO}_3$ ) deposited, inside the cracks and along joint planes in the matured coals, from mud or water that percolates through the coal beds.
- (ii) Sedimentary materials (slate, clay, pyrites, etc.) deposited simultaneously with the coal-forming material and present in definite layers in the coal, and
- (iii) Sand and clay mixed with coal from the roof and floor of the mine.

This portion of ash can be removed by selective mining and cleansing process (hand picking, washing, etc.).

*Inherent Ash* (oxides of Na, Mg, Ca, K & Si) arises from the mineral matter originally present in the cellulosic plant debris from which coal was formed. It rarely amounts to more than 2%.

*Adventitious* (Non-essential) mineral matter (clayey or silicious) present in mud or water in contact with the decomposing vegetation (during the anaerobic decay state) gets intimately mixed with coal or is present as dirt bands alternate with purer coal layers. The amount of adventitious ash varies widely and may go upto 10%. The inherent and adventitious mineral matter cannot be removed by cleansing operations and together constitute what is known as 'Fixed Ash'

*Significance*

Ash reduces the heating value of coal. There is a heat loss of about 1.5%



for each 1% ash present in coal. It increases transportation, handling and storage costs. The furnaces may have to be shut down for the removal and disposal of ash and increased labour costs are involved.

The chemical composition of ash, which is determined by the usual methods of analysis, differs from coal to coal and usually varies between the following limits:

Constituent	%	Constituent	%
SiO <sub>2</sub>	40-60	MgO	0.5-5
Al <sub>2</sub> O <sub>3</sub>	20-40	TiO <sub>2</sub>	0-3
Fe <sub>2</sub> O <sub>3</sub>	2-25	Na <sub>2</sub> O + K <sub>2</sub> O	1-6
CaO	1-15	SO <sub>3</sub>	0.2-15

As coal (or coke formed from it) is used as a reducing agent in several metallurgical operations, the composition of the ash affects the slag and metal composition and its characteristics, and is the most important factor governing the selection of a proper flux.

The fusion temperature of ash is of considerable importance and is closely related to its composition. In general, it has been found that ash containing Al<sub>2</sub>O<sub>3</sub> and SiO<sub>2</sub> in the ratio in which they are present in pure dehydrated clay Al<sub>2</sub>O<sub>3</sub> · 2SiO<sub>2</sub> (45.8% Al<sub>2</sub>O<sub>3</sub> + 54.2% SiO<sub>2</sub> by weight) is the most infusible (called refractory ash), and the fusion temperature decreases with increasing proportion of basic oxides like Na<sub>2</sub>O, K<sub>2</sub>O, MgO, CaO and FeO.

If the ash has low softening temperature, it fuses when coal is burnt on grates, and lumps of ash (called 'clinker') get deposited on the fire bars. This blocks the grate holes and spaces between coal particles; passage of air becomes irregular and restricted, and uneven heating takes place. This leads to increased clinkering. Clinker removal from grates is very difficult and laborious. Some coal particles may get embedded in the clinkers and escape combustion, thus leading to loss of fuel. Melted fly ash may be deposited on boiler tubes restricting heat transfer.

Molten slag from low melting ash penetrates into the pores of the refractory lining of the boiler or the furnace. Difference in the coefficients of expansion and contraction of the slag and the refractory material causes Spalling of the refractory lining thereby reducing its life.

Presence of some high melting ash is, however, necessary to protect the grates (in steam generation, producer gas and water gas manufacture) from direct contact with incandescent coal, which might cause oxidation of the grate bars.

### 5.3.1 Determination of Ash Content of a Coal/Coke sample

#### Procedure

Place the porcelain/silica capsule or platinum crucible containing dried coal (from the inherent moisture test), without cover, in a muffle furnace at a low temperature and gradually raise the temperature to 700°C. Stir the



residue with a platinum or nichrome wire (to hasten ignition) and ignite for half an hour at a temperature between 700 and 750°C. Moisten the residue with a drop or two of alcohol. If black particles appear (due to the presence of unburnt carbon), continue ignition for another 15 minutes. Cool in a desiccator and weigh. Repeat the process of ignition, cooling and weighing until the difference in weights between two successive weighings is less than 1 mg.

For tests on coke, heat the capsule or crucible containing dried coke in a muffle furnace or over a burner to redness. Finish the ignition to constant weight ( $\pm 1$  mg) at a temperature between 900 and 950°C.

### Precautions

- (1) To avoid mechanical loss due to rapid expulsion of volatile matter, the temperature should be raised at a slow rate.
- (2) For coals containing high percentage of calcite and pyrite, reproducible results are not obtained because of the varying amounts of sulphate-sulphur being retained in the ash. To overcome this difficulty, the sample is heated at a lower temperature ( $\sim 500^\circ\text{C}$ ) for a longer duration of time which ensures complete oxidation and expulsion of pyrite sulphur before the decomposition of calcite takes place when the temperature is raised to 750°C.

### Observations and Calculations

Weight of empty and previously ignited capsule or crucible = A g

Weight of capsule + air dried sample = B g

Weight of capsule + oven dried sample = C g

Weight of capsule + residue, after ignition = D g

Ash content (Air dry basis)  $= \frac{D - A}{B - A} \times 100\%$

Ash content (Oven dry basis)  $= \frac{D - A}{C - A} \times 100\%$

### Exercise

135. What is meant by 'corrected' and 'uncorrected' ash?

## 5.4 Volatile Matter

When coal is heated gradually in the absence of air, moisture and occluded gases escape first. As the temperature rises, there is evolution of  $\text{H}_2\text{S}$  and some unsaturated hydrocarbons. At about 350°C, active decomposition of coal begins and continues with rise in temperature, accompanied by evolution of large quantities of gas and tarry vapours consisting mainly of hydrocarbons. Around 700°C, the amount of hydrogen in the evolved gases



increases. Hydrogen is the major constituent of the gases liberated at higher temperature.

The volatile matter expelled thus is not present as such in coal but results from thermal decomposition of the coal material. The total amount of the volatile matter evolved and its composition depend, in addition to the quality of coal, on the temperature, rate of heating and the time for which heating is continued. For comparable results, therefore, conditions specified by ASTM are generally followed.

Volatile matter is the percentage loss in weight of coal (minus % of moisture) when it is heated in the absence of air for exactly 7 minutes at  $950 \pm 20^\circ\text{C}$ , in a crucible of standard dimensions.

### *Significance*

The volatile matter of coals may consist of combustible gases (like  $\text{CO}$ ,  $\text{H}_2$ ,  $\text{CH}_4$  and other hydrocarbons) and incombustible gases (like  $\text{CO}_2$  and  $\text{N}_2$ ). The presence of incombustible gases is always undesirable as they do not have any heating value. Volatile matter of coals may be as high as 50% and when such coals are burnt, a large proportion of the fuel distils over as gas or vapour which burns with the production of flame. Coals with high volatile matter will therefore burn with long smoky flames, the smoke causing pollution of the environment. The calorific intensity of such coals is less since the heat produced is distributed over large space. Such coals are therefore not suitable for production of steam where intense heat is required. Coals with high volatile matter are, however, suitable for manufacture of coal gas, particularly when the recovery of by-products is desired.

For complete combustion of the large volatile matter, secondary air will be required and the volume of the furnace will have to be increased to prevent the escape of unburnt vapours which otherwise will lead to loss of heat. The furnace design therefore depends on the volatile matter.

Whereas it is very easy to ignite a coal with a high volatile matter, burning of low volatile coals necessarily requires forced draft; its intensity increasing with decreasing volatile matter.

Caking quality of coal varies with its volatile matter. Coals containing volatile matter between 20% and 30% are most suited for the production of metallurgical coke. Coking power decreases with increase or decrease of volatile matter and coals having less than 14% volatile matter have no caking tendency.

### *5.4.1 Determination of Volatile Matter of a Coal Sample*

#### *Procedure*

Weigh exactly about 1 g of the sample in a previously dried (at  $950 \pm 20^\circ\text{C}$ ) and weighed platinum crucible (diameter 2.5-3.5 cm, height 3-3.5 cm, capacity 10-20 ml) with a closely fitting lid which has a vent for the escape of volatile matter. Spread the sample evenly, close with the lid and place in a muffle furnace maintained at  $950 \pm 20^\circ\text{C}$  and shut the door. After heating



for exactly 7 minutes, take out the crucible and first bring down its temperature rapidly (to avoid oxidation of the contents) by placing it on a cold iron plate and then transfer the warm crucible to a desiccator to bring it to room temperature. Take the final weight of the crucible and the contents.

#### Precaution

If 'Sparking' (mechanical loss due to suddenly heating the sample) is observed, the sample-containing crucible should first be heated to raise the temperature to  $600 \pm 50^\circ\text{C}$  in 6 minutes, followed by heating for exactly 6 more minutes at  $950 \pm 20^\circ\text{C}$ .

#### Observations and Calculations

Let the weight of empty crucible  $= A \text{ g}$

Weight of crucible + sample, before heating  $= B \text{ g}$

Weight of crucible + sample, after heating  $= C \text{ g}$

$$\% \text{ volatile matter} = \left[ \frac{B-C}{B-A} \times 100 - \% \text{ moisture} \right]$$

### 5.5 Fixed Carbon

The residue, remaining after the volatile matter of coal has been expelled, contains the mineral matter originally present and the non-volatile or 'Fixed' carbon. The fixed carbon in coal is thus calculated as follows:

$$\% \text{ Fixed carbon} = 100 - (\% \text{ moisture} + \% \text{ ash} + \% \text{ volatile matter}) \quad (5.2)$$

'Fixed' carbon varies inversely with volatile matter. It represents the amount of coal that will burn in the solid state with primary air forced or drawn through the hot bed of coal, thus having a bearing on furnace design. High 'Fixed' carbon indicates high calorific intensity. Carbon contributing much towards the heating value, a high percentage of 'Fixed' carbon ascertains high calorific value. The following empirical relation-ship (Goutel formula) holds true for high ranking coals:

$$Q = 82 \times \text{FC} + \alpha \times \text{VM} \quad (5.3)$$

where  $Q$  = calorific value of coal (cals/g)

$\text{FC}$  = % of fixed carbon

$\text{VM}$  = % of volatile matter

and  $\alpha$  = a factor that depends on the nature of volatile matter and its value decreases with rise in volatile matter.

#### Exercise

136. (i) 2.5 g of a coal sample was taken in a silica crucible weighing 19.35 g. After heating in an electric oven at  $105-110^\circ\text{C}$  for 1



hour, the crucible weighed 21.765 g. The residue was then ignited at 770-750°C to a constant weight when the crucible weighed 19.595 g.

- (ii) In another experiment, 2.5 g of the same sample was heated in a silica crucible (weighing 19.345 g), covered with a vented lid, at a temperature of  $950 \pm 20^\circ\text{C}$  for exactly 7 minutes. After cooling, the crucible weighed 20.873 g.
- (iii) Calculate the percentage of fixed carbon and the calorific value of coal using Goutel's formula, value of  $\alpha$  being 80

## 5.6 Ultimate Analysis

It is the determination of carbon, hydrogen, nitrogen, sulphur, phosphorus, ash and oxygen (by difference) in coal. The analysis is exact and helpful

- (1) In calculating the calorific value of coal by Dulong's formula

$$\text{Gross or Higher Calorific Value (H.C.V.)} = \frac{1}{100} [8080C + 34460 (H - \frac{O}{8}) + 2240S] \text{ Kcal/kg} \quad (5.4)$$

$$\text{\& Lower Calorific Value (L.C.V.)} = \text{H.C.V.} - \frac{9}{100} H \times 587 \text{ Kcal/kg} \quad (5.5)$$

where C, H, O and S represent the percentage of the respective elements.

- (2) In calculating the amount of air required for perfect combustion of the coal and
- (3) In ascertaining whether a particular coal can be used in metallurgical operations or not.

## 5.7 Carbon and Hydrogen

Carbon being the major constituent of coal, its amount determines, to a large extent, the calorific value of the coal. Also, the carbon content increases with the degree of alteration in the natural coalification process (wood ~ 50%, peat 50-60%, lignites 60-75%, bituminous 75-92%, anthracite 92-98%). The percentage of carbon is therefore an important factor in assessing the rank and age for classifying coals. Coals with high carbon content usually require a small combustion chamber although there is no direct relation between the two.


The percentage of hydrogen in coal (3-6%) depends to a large extent on the hydrogen content of the original vegetable matter (3.5-8%) and to a small extent on the degree of transformation. Hydrogen content has a large bearing on the calorific value of the coal because the heating value of hydrogen per unit weight (34460 k cal/kg) is more than four times the heating value of carbon (8080 k cal/kg). However, a small part of this heat is lost in evaporating the water formed from the combustion of hydrogen.



Hydrogen is mostly associated with volatile matter of coal and therefore has a bearing on the size of the combustion chamber and to some extent on the suitability of coal for a specific use or purpose.

#### Principle of Determination

Carbon and hydrogen are determined by burning a weighed quantity of coal, in presence of CuO, in a stream of oxygen free from moisture and CO<sub>2</sub>. The carbon and hydrogen of the sample are converted into CO<sub>2</sub> and H<sub>2</sub>O:



After complete oxidation and purification from interfering substances, the products of combustion are passed first through a water absorbing unit and then through a CO<sub>2</sub> absorbing unit. The increase in weights of these units gives respectively the weights of H<sub>2</sub>O and CO<sub>2</sub> formed from which the percentage of hydrogen and carbon present in the sample can be calculated:

$$\% \text{ Hydrogen} = \frac{2}{18} \times \frac{\text{weight of H}_2\text{O formed}}{\text{weight of coal burnt}} \times 100 \quad (5.8)$$

$$\% \text{ Carbon} = \frac{12}{44} \times \frac{\text{weight of CO}_2 \text{ formed}}{\text{weight of coal burnt}} \times 100 \quad (5.9)$$


### 5.8 Sulphur in Coal

Sulphur content of coals generally varies from 0.5 to 3%, with some exceptions of higher amounts. It occurs principally in two forms:

- (a) As iron pyrites (occasionally as gypsum, CaSO<sub>4</sub> · 2H<sub>2</sub>O, also), mixed along with coal, most of which can be removed by
  - (i) hand picking from larger sizes of coal, and
  - (ii) gravity separation by washing smaller sizes of coals with water.
- (b) As organic sulphur compounds forming part of the coal itself. The organic sulphur usually
  - (i) ranges from 0.5 to 0.6%.
  - (ii) is almost uniformly distributed throughout the coal material, and
  - (iii) can not be removed by 'cleansing' operations.

#### Significance

Although sulphur does have some heating value (2240 k cal/kg), SO<sub>2</sub> and SO<sub>3</sub> formed during the combustion of sulphur-containing coals are extremely





$\text{CaSO}_4 + \text{SiO}_2$  (usually present

in coals in small amounts)  $\xrightarrow{\text{heat}}$   $\text{CaSiO}_3 + \text{SO}_3$  (5.12)


harmful. The gases cause environmental pollution and in moist atmosphere produce acids ( $\text{H}_2\text{SO}_3$  and  $\text{H}_2\text{SO}_4$ ) which cause corrosion of the metallic equipment around.

We can have an idea of the pollutional hazards from the fact that sulphur oxides equivalent to 3 tons of concentrated  $\text{H}_2\text{SO}_4$  are discharged daily into atmosphere by a small Thermal Power Plant burning per day 100 tons of a coal that contains only 1% sulphur.

When sulphur-containing coals are carbonised, 20-30% sulphur passes into coal gas in the form of  $\text{H}_2\text{S}$ ,  $\text{CS}_2$  and thiophene from which only  $\text{H}_2\text{S}$  is removed before the gas is supplied for domestic purposes.

Most of the 70-80% sulphur retained in coke (present partly as  $\text{FeS}$ ,  $\text{CaS}$  or elemental sulphur) is oxidised to  $\text{SO}_2$  when coke is burned and escapes to atmosphere. A part of  $\text{FeS}$  that escapes oxidation under mildly reducing conditions might fuse and lead to clinkering problem. When such cokes are used for metallurgical purposes, some sulphur might get mixed with metals and adversely affect their characteristics. Presence of sulphur in the coal used in ceramic industry adversely affects the product characteristics.

Rapid oxidation of iron pyrites present in coals exposed to air may lead to disintegration of the coal lumps thereby exposing fresh and easily oxidisable



coal surface. Presence of iron pyrites is thus one of the factors responsible for spontaneous ignition of coal samples when exposed to air.

### 5.8.1 Determination of Sulphur Content of a Sample of Coal

#### (a) Eschka Method

##### Reagents Required



- (1) Barium chloride solution (5%)
- (2) Bromine solution (saturated)
- (3) Concentrated hydrochloric acid
- (4) Dilute hydrochloric acid
- (5) Sodium hydroxide solution (5N)
- (6) Methyl orange indicator solution
- (7) Silver nitrate solution
- (8) Eschka-Mixture—Thoroughly mix 2 parts by weight of sulphur-free  $\text{MgO}$  with 1 part by weight of sulphur-free anhydrous  $\text{Na}_2\text{CO}_3$  and grind to pass through an ordinary flour sieve.

##### Theory


A known weight of powdered coal is fused with Eschka-mixture in presence of air. The sulphur in coal is oxidised to  $\text{SO}_2$  which is absorbed by




Eschka-mixture to produce the corresponding sulphites:



The sulphites are extracted with water and oxidised to sulphate using bromine water



On adding barium chloride solution to the slightly acidified extract, the sulphate is precipitated as  $\text{BaSO}_4$  which is filtered, washed, ignited and weighed.



From the weight of  $\text{BaSO}_4$ , the percentage of S in coal can be calculated as follows:

$$\% \text{ S} = \frac{32}{233} \times \frac{\text{weight of BaSO}_4}{\text{weight of coal}} \times 100 \quad (5.19)$$

#### Procedure

Transfer about 1 g of accurately weighed coal powder (60 mesh) to a silica, porcelain or platinum crucible. Add about 3 g of Eschka-mixture, mix thoroughly and cover with about 1 g more of Eschka-mixture. Place the crucible in a slightly slanting position in a muffle furnace at room temperature and heat gradually so as to raise the temperature to  $850 \pm 50^\circ\text{C}$  in about 1 hour. Continue heating at this temperature for another 1 hour with occasional stirring with a stout nickel wire. When no black carbon particles are visible, allow the crucible to cool to room temperature. Remove the contents to a 200-ml beaker. Extract the residue completely using about 100 ml of hot distilled water. Heat for about half an hour and filter under suction. Wash the residue with hot water. Collect the filtrate and washings in a beaker, add 10-15 ml of saturated bromine solution and heat gently for a few minutes. Acidify with concentrated HCl and boil off the liberated bromine. Add two drops of methyl orange and just neutralise with NaOH solution. Add 1 ml of dilute HCl and heat the solution to boiling. Add slowly from a pipet, while stirring constantly with a glass rod, 10-15 ml of hot 5 per cent solution of barium chloride. Cover the beaker with a clock glass, boil for 15 minutes and keep the solution hot, below its boiling temperature, by placing the beaker on a low temperature hot plate for 1 hour.

Filter, by decantation, through a whatman filter paper No. 540/40. Transfer the precipitate to the filter paper and wash with small portions of hot distilled water until the washings are free from chloride (test a few drops of the filtrate with  $\text{AgNO}_3$ ).


Hold the moist filter paper around the precipitate, loosely to avoid spattering, and place it in a clean platinum, porcelain or silica crucible (previously ignited to a temperature of about  $900^\circ\text{C}$ , cooled in a desiccator and weighed).



Cover the crucible with lid loosely to permit free access of air, place in a slightly inclined position in a cold muffle furnace and gradually raise the temperature to dry and smoke off the paper. Then raise the temperature to above 900°C and ignite to constant weight. Cool in a desiccator and weigh. Run a blank using the same amounts of reagents as in the regular determination.

#### Precautions

1. The reagents used must be sulphur-free.
2. The sample should be heated with Eschka-mixture at a low heat in the beginning to avoid rapid expulsion of the volatile matter which may lead to
  - (i) mechanical loss due to decrepitation, and
  - (ii) incomplete absorption of  $\text{SO}_2$  by Eschka-mixture.
3. A jet of hot water from a wash bottle may be used to aid the transfer of the precipitate to the filter paper. Any precipitate sticking to the walls of the beaker or to the glass rod may be loosened with a 'policeman'.
4. To avoid reduction of the  $\text{BaSO}_4$  precipitate by carbon of the filter paper during ignition, the paper should be



charred first at slow heat, without inflaming, and then the carbon should be slowly burnt off at a low temperature in free access of air.

#### Observations and Calculations

Let the weight of coal sample taken	= W g
Weight of $\text{BaSO}_4$ obtained from coal sample	= A g
Weight of $\text{BaSO}_4$ obtained in blank determination	= B g
% S in the sample	$= \frac{32}{233} \times \frac{(A - B)}{W} \times 100 \quad (5.10)$

#### Exercises

137. Why is the precipitation of  $\text{BaSO}_4$  carried out in a medium made only slightly acidic with HCl?
138. What is Coprecipitation? How can the error due to coprecipitation of  $\text{Ba}(\text{NO}_3)_2$  and  $\text{BaCl}_2$  be avoided?

### 5.9 Nitrogen in Coal

Nitrogen content of coals generally varies between the limits 1-1.8% and comes from the proteins present in the parent vegetable matter. It has no calorific value and so its presence in coal is undesirable. If the combustion results in a very high temperature (as in Thermal Power Stations), a part of



nitrogen is converted into its oxides which escape along with the flue gases and cause atmospheric pollution. During carbonisation, nitrogen of coal is converted to  $\text{NH}_3$  which can be recovered from the volatile matter (coal gas) by scrubbing with water or dilute  $\text{H}_2\text{SO}_4$ .

### 5.9.1 Determination of Nitrogen in a Coal sample (Kjeldahl Gunning method)

#### Reagents Required


1. Standard sulphuric acid (N/10)
2. Standard sodium hydroxide solution (N/10)
3. Sodium hydroxide solution (50%)
4. Concentrated sulphuric acid
5. Potassium sulphate
6. Anhydrous copper sulphate
7. Sucrose
8. Methyl red indicator solution
9. Red litmus paper.

#### Principle


A known weight of powdered coal is digested with concentrated  $\text{H}_2\text{SO}_4$  in presence of  $\text{K}_2\text{SO}_4$  (to raise the boiling point of  $\text{H}_2\text{SO}_4$  and thus help in digestion) and  $\text{CuSO}_4$ , selenium powder or  $\text{CuSeO}_3 \cdot 2\text{H}_2\text{O}$  (to act as catalyst). The nitrogen in coal gets converted into ammonium sulphate




As the solution becomes clear, it is treated with excess of  $\text{NaOH}$  or  $\text{KOH}$  and distilled when  $\text{NH}_3$  gas is evolved:



The ammonia so liberated is absorbed into a known volume (present in excess) of standard sulphuric acid:



and the unused acid (excess) is back titrated with standard  $\text{NaOH}$  solution using methyl red indicator:



The percentage of nitrogen in coal is calculated as follows:

$$\% \text{N} = \frac{\text{ml of acid used} \times \text{normality of acid} \times 1.4}{\text{weight of coal taken}} \quad (5.25)$$

#### Procedure

Weigh accurately about 1 g of powdered coal and transfer it to a Kjeldahl's flask. Add about 10 g of  $\text{K}_2\text{SO}_4$  and either 0.2 g of Se powder or 0.5 g of anhydrous  $\text{CuSO}_4$  or 0.3 g of cupric selenite dihydrate ( $\text{CuSeO}_3 \cdot 2\text{H}_2\text{O}$ ).



2H<sub>2</sub>O) followed by 25 ml concentrated H<sub>2</sub>SO<sub>4</sub> along the sides of the Kjeldahl's flask to wash down any powder sticking to the neck or the sides of the flask. Close the flask with the loose glass stopper and shake to mix the contents. Place the flask in an inclined position and heat gently below the boiling point of the solution until the initial frothing ceases. Then raise the temperature to the boiling point of the solution and continue the digestion for at least two hours after the contents of the flask have become almost colourless.

Then cool the Kjeldahl's flask and transfer its contents to a round-bottom distillation flask. Wash the Kjeldahl's flask well with distilled water and transfer the washings to the distillation flask so that the total volume of the contents of the distillation flask are about 300 ml. Add a few chips of red litmus paper and fit the flask with a thistle funnel and a Kjeldahl's trap (to prevent splashing of the alkaline solution to the condenser during heating). Connect the Kjeldahl's trap to a condenser whose other end dips in 50 ml of N/10 H<sub>2</sub>SO<sub>4</sub> taken in a conical flask. Through the thistle funnel, add concentrated NaOH solution until the contents of the flask are distinctly alkaline, as evidenced by the change in colour of the litmus paper from red to blue. Distil the contents of the flask for about one hour, maintaining the solution alkaline throughout. Discontinue boiling, and disconnect the flask, when the volume of the distillate in the conical flask becomes about 200 ml, and wash down the condenser with distilled water into the conical flask. Add 3-4 drops of methyl red indicator and titrate with N/10 NaOH until the colour changes from red to yellow and record the volume of acid used as A ml. Make a blank on 1 g of sucrose using the same amounts of other reagents as in the estimation on coal and record the volume of N/10 alkali used as B ml.

#### *Precautions*

- (1) All the reagents used must be nitrogen-free.
- (2) Before transferring the digested solution to the distillation flask, the Kjeldahl's flask should be cooled under tap. Also, dilution of the solution in distillation flask should be slow with shaking and cooling.
- (3) To prevent bumping during distillation, a few porcelain chips or glass beads or about 1 g granulated Zn should be added.
- (4) The solution in the distillation flask should be kept only moderately alkaline throughout. A considerable excess of NaOH often causes excessive frothing.
- (5) When the solution froths excessively, a pea-sized piece of paraffin wax should be added to control it.
- (6) To prevent back suction, the tube of the condenser, dipping in standard acid solution, should end in the shape of a funnel.

#### *Observations and Calculations*

Let the weight of coal taken

= w g



Volume of N/10 NaOH used in Blank

(=amount of acid taken)

= B ml

Volume of N/10 NaOH used in sample

determination (=amount of acid left unused)

= A ml

Therefore, Amount of acid neutralised by  $\text{NH}_3$  = (B - A) ml N/10  $\text{H}_2\text{SO}_4$

= (B - A) ml N/10  $\text{NH}_3$  solution

$$= (B - A) \times \frac{1}{10} \times \frac{1}{1000} \times 17 \text{ g } \text{NH}_3$$

$$= (B - A) \times \frac{1}{10 \times 10^3} \times 17 \times \frac{14}{17} \text{ g N}$$

$$\text{Therefore, } \% \text{ N} = \frac{(B - A) \times 14}{10 \times 10^3} \times \frac{100}{w} = \frac{(B - A) \times 1.4}{w} \times \frac{1}{10} \quad (5.25)$$

### Exercises

139. Why is it necessary to add sufficiently large amount of concentrated  $\text{H}_2\text{SO}_4$  during digestion?
140. What modification in the procedure is required if  $\text{HgO}$  or  $\text{Hg}$  is used as a catalyst during digestion with  $\text{H}_2\text{SO}_4$ ?
141. How does addition of granulated zinc prevent bumping?

### 5.10 Oxygen Content of Coal

With the increase in the degree of transformation from wood to anthracite, the percentage of oxygen regularly decreases (wood = 35-43%; peat = 30-40%; lignites = 20-30%; bituminous = 5-20%; anthracite = 2-5%). The rank of the coal is therefore related to the oxygen content and decreases with increasing amount of oxygen. Oxygen in coal is supposed to be combined with hydrogen. An equivalent amount of hydrogen is therefore already burnt, i.e., not available for combustion, leading to a decrease in calorific value. It has been found that a 1% increase in oxygen content decreases the calorific value by about 1.7%. Increase in oxygen content of coals increases their tendency to retain inherent moisture. In case of bituminous coals, the caking power is known to decrease with increasing oxygen content. There is no direct method for determining the oxygen content of coal and has to be calculated by deducting the combined percentage of C, H, N, S and ash from 100.

$$\% \text{ Oxygen} = 100 - \text{percentage of } (C + H + N + S + \text{Ash}) \quad (5.26)$$

### Exercises

142. (a) A sample of coal containing C, H, N, S and O was analysed as follows:
  - (i) 0.24 g of the sample on combustion gave 0.792 g of  $\text{CO}_2$  and 0.0216 g of  $\text{H}_2\text{O}$ .
  - (ii) 1.4 g of the sample was Kjeldahlised and the ammonia liberated was absorbed in 50.0 ml of N/10  $\text{H}_2\text{SO}_4$ . The resultant solution



- required 10.0 ml of N/10 NaOH for complete neutralisation.
- (iii) 3.2 g of the sample was analysed by Eschka method and gave 0.233 g of  $\text{BaSO}_4$ .  
Using Dulong's formula, calculate the Gross and Net calorific value of the coal.
- (b) Of the two types of Coal Analysis-Proximate and Ultimate-which one is more useful and why?

### 5.11 Combustion of a Carbonaceous Fuel—Flue Gas

When a fuel is burnt in air, the carbon and hydrogen of the fuel are converted into  $\text{CO}_2$  and  $\text{H}_2\text{O}$  as per the following equation:



and heat is liberated. The mixture of the gases which comes out of the furnace (combustion chamber) is known as Flue Gas. If the theoretical amount of air (containing exactly the same amount of  $\text{O}_2$  as is required in accordance with the above reaction) is supplied and the combustion is complete, the flue gas consists of (in addition to water vapour)  $\text{CO}_2$  and  $\text{N}_2$ . However, it is not possible to complete the combustion with the theoretical amount of air, and either a part of fuel escapes combustion or incomplete combustion of C to CO stage takes place. The flue gas, therefore, may contain small amounts of CO and/or hydrocarbons ( $\text{C}_x\text{H}_y$ ). Escape of these gases (CO and  $\text{C}_x\text{H}_y$ ) to the atmosphere causes environmental pollution. Also, a part of the total heat, that could be available from the fuel, is thus lost. On the other hand, if a large excess of air is used, the flue gas also contains this unused extra oxygen supplied. Also, a large excess of air added lowers the flame temperature (calorific intensity) and carries away a lot of sensible heat.

Hence for efficient utilisation of heat available from a fuel, an optimum amount of air should be supplied. This amount cannot be theoretically computed. Other factors that affect efficient combustion are intimate mixing (or contact) of air and fuel and sufficient time to allow completion of combustion (governed by rate of combustion). Both these factors depend on the furnace design.

Whether efficient combustion is taking place or not is determined by the actual amounts of CO,  $\text{O}_2$  or other hydrocarbons present in the flue gas. Hence the analysis of the flue gas is of prime importance.

A large excess of CO in the flue gas indicates incomplete combustion, which means amount of air supplied is not sufficient. A large excess of  $\text{O}_2$  in the flue gas indicates that air supply is much in excess. If both CO and  $\text{O}_2$  are simultaneously present in the flue gas in appreciable amounts, combustion is incomplete, irregular and non-uniform, and improvement in the design of the combustion chamber, furnace or engine is required.




### 5.11.1 Determination of the percentage of $\text{CO}_2$ , $\text{CO}$ , $\text{O}_2$ and $\text{N}_2$ in a Flue Gas (or Automobile Exhaust) by Orsat's Apparatus.

#### Principle

A measured volume of the gas to be analysed is taken in a graduated burette which is connected through a capillary manifold to a series of pipets containing solutions of suitable absorbent reagents. The gas is successively forced through these solutions in a specific order. Each reagent removes a single constituent from the sample. The decrease in volume of the flue gas sample in each step gives the volume of the constituent removed in that step.


#### Solution of Absorbent Reagents

(i) *Absorbent for  $\text{CO}_2$*  is a solution of 300 g of KOH pellets in one litre of distilled water prepared by stirring with a glass rod. The solution is stored in a rubber stoppered glass bottle and is decanted before use. When the gas sample is led into this solution,  $\text{CO}_2$  content is retained by the solution as per the following reaction:




(ii) *Absorbent for  $\text{O}_2$*  is prepared by adding 80 g of pyrogallol crystals to 500 ml of KOH solution [prepared in (i)] in a glass-stoppered bottle kept in a cool place till dissolution is complete. When the gas sample is forced into this solution, the oxygen content is used up in oxidising pyrogallol.

(iii) *Absorbent for  $\text{CO}$*  is a solution of 75 g of  $\text{Cu}_2\text{Cl}_2$  in 600 ml conc. HCl and 400 ml distilled water stored in a glass bottle containing copper turnings or wire.  $\text{CO}$  of the gas sample, when it is passed through this solution, is retained in the form of a complex:



Sometimes the gas sample, after the major portion of its  $\text{CO}$  content has been absorbed by acid cuprous chloride, is passed through another pipet containing Cuprous Sulphate- $\beta$ -Naphthol solution to remove the last trace of  $\text{CO}$  which combines with cuprous sulphate to form more stable  $\text{Cu}_2\text{SO}_4 \cdot 2\text{CO}$  which does not give up  $\text{CO}$  as does  $\text{Cu}(\text{CO})\text{Cl} \cdot 2\text{H}_2\text{O}$ .



#### Procedure

##### 1) Preparation of the apparatus

After thoroughly cleaning the apparatus (Figure 11) apply grease to all the stoppers. Fill the jacket (A) around the burette (B) complete with water and the aspirator or the levelling bottle (C) upto two thirds with a confining liquid (a 25% NaCl solution acidified with dilute HCl to which a few drops of methyl red have been added). Take the three solutions, i.e.,  $\text{CO}_2$  absorbent,  $\text{O}_2$  absorbent and  $\text{CO}$  absorbent in pipets  $p_1$ ,  $p_2$ , and  $p_3$ , respectively. Close the stop cocks  $a_1$ ,  $a_2$ ,  $a_3$  and open the three way stop cock D to atmosphere.



Raise the aspirator (C) till the burette is filled with the confining liquid. Now close cock D, open cock  $a_1$  and lower C till the level of the solution in pipet  $p_1$  is raised up to the fixed mark  $m_1$ . Close cock  $a_1$ . In a similar way, bring the level of the solutions in pipets  $p_2$  and  $p_3$  to the fixed marks  $m_2$  and  $m_3$  respectively and close  $a_2$  and  $a_3$ .




Fig. 11 Orsat Apparatus.

- |   |                           |
|---|---------------------------|
| A—Jacket                                    | B—Burette                 |
| C—Levelling bottle or Aspirator             | D—Three way stopcock      |
| E—Capillary manifold                        | F—Clamp stand             |
| U—Tube containing anhydrous $\text{CaCl}_2$ | G—Wooden case             |
| $a_1, a_2, a_3$ stop cocks                  | R—Collapsible rubber bulb |
| $m_1, m_2, m_3$ fixed marks                 | $p_1, p_2, p_3$ pipets    |

## (2) Filling the burette with the sample

Open cock D to atmosphere and raise C to expel air in the burette. Connect cock D to the flue gas supply (through U-tube containing anhydrous  $\text{CaCl}_2$  secured by glass wool to retain any smoke particles and/or moisture present in the sample) and lower C to draw the gas into the burette. The gas gets mixed with the small amount of air present in the capillary manifold. Open cock D to atmosphere and expel the gas by raising C. Repeat the process of drawing in and expelling the gas twice or thrice. Finally fill the burette completely with the gas, open D to atmosphere and raise the height of the aspirator C very carefully so as to equalise the levels of the liquid in



the aspirator and in the burette in which it should stand at zero mark. Close the cock D. The burette now contains 100 ml of the gas under atmospheric pressure.

(3) *Determining the percentage of  $\text{CO}_2$*

Open  $a_1$  and raise C to force the gas into  $p_1$ . A portion of the  $\text{CO}_2$  content gets absorbed by KOH solution present in  $p_1$ . Lower C to take the gas back into the burette and again drive it into  $p_1$ . Repeat the process four to five times which should completely remove  $\text{CO}_2$  from the sample gas. Lower C till the solution in pipet  $p_1$  stands at the mark  $m_1$  and close  $a_1$ . Bring the confining liquid in the aspirator and in the burette to the same height and record the volume of the gas in the burette. To be sure that all the  $\text{CO}_2$  has been absorbed, repeat the whole process with the same pipet ( $p_1$ , containing KOH) till the two volume readings are identical. Let the constant reading be  $V_1$ . The decrease in the volume of the gas in the burette, i.e.,  $V_1$  ml is then equal to the percentage of  $\text{CO}_2$  in the flue gas.

(4) *Determining the percentage of  $\text{O}_2$*

Open  $a_2$  and force the residual gas into the pyrogallol solution contained in pipet  $p_2$  to effect the absorption of  $\text{O}_2$ . Ensure the complete absorption of  $\text{O}_2$  by a number of passes of the gas into  $p_2$ , raise the level of solution in  $p_2$  to  $m_2$  and close  $a_2$ . Record the constant level of the confining liquid in the burette after bringing the gas to the atmospheric pressure (i.e., equalise the levels of the liquid in the burette and the levelling bottle). Let the constant reading be  $V_2$ . Then percentage of  $\text{O}_2$  in the flue gas =  $(V_2 - V_1)$ .

(5) *Determining the percentage of CO*

Open  $a_3$  and force the residual gas into  $p_3$  containing acid cuprous chloride solution. Repeat as in (3) or (4) above with the difference that after each passage of the gas into the pipet  $p_3$  and also before recording the volume of residual gas, pass the gas into the KOH pipet ( $p_1$ ) to remove HCl vapours taken up from the acid cuprous chloride. Let the constant level, after complete absorption of CO, stand at  $V_3$ . Then percentage of CO in the flue gas =  $(V_3 - V_2)$ .

(6) *Determining the percentage of  $\text{N}_2$*

The gas left after the absorption in  $p_1$ ,  $p_2$  and  $p_3$  consists of  $\text{N}_2$  which may contain small amounts of unburnt  $\text{H}_2$  and/or hydrocarbons. Unless a detailed analysis is desired, these gases are reported as  $\text{N}_2$ .

$$\begin{aligned}\text{Percentage of } \text{N}_2 \text{ in the flue gas} &= 100 - [V_1 + (V_2 - V_1) + (V_3 - V_2)] \\ &= 100 - V_3\end{aligned}$$



*Precautions*

1. Before filling the pipets with the respective solutions, the apparatus must be checked for leaks. (For this, close the cocks  $a_1$ ,  $a_2$ ,  $a_3$  and open the cock D to atmosphere. Raise C to fill the burette with the confining liquid up to some definite level. Close D and slowly move the levelling bottle up and down. Any movement in the level of the liquid in the burette indicates a leak, which should be checked by properly greasing the stop cocks.
2. While expelling the air from the burette or forcing the gas into absorbent pipets by raising the level of the aspirator, care should be taken that no liquid enters the capillary manifold.
3. To avoid any contact between the atmospheric gases and the absorbent, the open end of the storage bulbs attached to the pipets should be closed with a collapsible rubber bulb.
4. While reading the volume of the gas in the burette, before or after absorption in a pipet, the aspirator must be held very close to the burette and the levels of the liquid in the burette and in the aspirator should be carefully adjusted to the same height (atmospheric pressure).

*Exercises*

143. What is the purpose of adding copper turnings or wire to the cuprous chloride solution?
144. Why are the pipets containing the absorbent solutions filled with glass tubes or beads?
145. What are the drawbacks of water being used as a confining liquid?
146. What is the purpose of adding a few drops of HCl and methyl red to the confining liquid?
147. Explain why it is necessary to follow a definite order for absorption of various constituents of a flue gas. List this order.
148. What is pyrogallol?
149. How does the presence of acidic gases like  $\text{SO}_2$ ,  $\text{H}_2\text{S}$ ,  $\text{HCN}$ , etc., in the flue gas affect the analysis?
150. How does the presence of  $\text{H}_2$  or unburnt hydrocarbons affect the analysis?
151. What is the effect of temperature and pressure on the analysis?
152. Why is the graduated burette surrounded by a water-jacket?
153. Name a few modern instrumental methods of gas analysis and compare the usefulness of the Orsat apparatus against them.
154. Distinguish between a fuel gas and a flue gas. What is the approximate composition of a flue gas?



## Ores and Alloys

### 6.1 Iron Ore

Iron is easily attacked by humid atmosphere. So native iron in nature is very rare. It occurs principally as oxides:

- |                                  |   |
|----------------------------------|---|
| (a) Hematite or Red Iron Ore     | — $\text{Fe}_2\text{O}_3$   |
| (b) Limonite or Brown Iron Stone | — $\text{Fe}_2\text{O}_3 \cdot \text{H}_2\text{O}$ or $\text{FeO}(\text{OH})$ |
| (c) Magnetite or Lode Stone      | — $\text{Fe}_3\text{O}_4$   |

Less abundant ores are sulphides and carbonate:

- |                                  |                    |
|----------------------------------|--------------------|
| (d) Iron pyrites                 | — $\text{FeS}_2$   |
| (e) Chalcopyrites                | — $\text{CuFeS}_2$ |
| (f) Siderite or Sphatic Iron Ore | — $\text{FeCO}_3$  |




The ores may be associated with small amounts of other metals like copper, cobalt, nickel, arsenic, molybdenum, chromium, etc. Some organic matter is also usually present. When the ores are to be used for making iron, the total iron content must be determined to ascertain the economic viability of the extraction process. The analysis involves the following steps:

#### (a) Preparation of solution of iron ore

About 2 g (accurately weighed by difference method) of finely pulverised ore sample is transferred to an open silica crucible. It is first heated gently and then the sample is ignited by gradually raising the temperature to redness. The residue is cooled and using a platinum or nickel spatula, it is transferred to a porcelain basin. The silica crucible and spatula are washed with three 10-ml portions of conc. HCl and the washings are transferred to the porcelain basin. The basin is covered with a large funnel and heated on a hot plate for about half an hour. The resulting solution is diluted to about 50 ml with distilled water and allowed to cool when the undissolved matter settles down. The supernatant liquid is transferred by decantation to a 250-ml measuring flask. The residue is again heated with about 50 ml of 1:1 HCl for about half an hour and the liquid transferred to the measuring flask as before. The residue is washed with two 10-ml portions of 1:1 HCl, the washings transferred to the measuring flask and the volume is made up to the mark.



The decomposition of the iron ore with acid involves the following reactions:





(b) *Reduction of  $\text{Fe}^{3+}$  to  $\text{Fe}^{2+}$*

Iron in a given solution is generally determined by titrating with a standard solution of  $\text{K}_2\text{Cr}_2\text{O}_7$  or  $\text{KMnO}_4$ . Both methods determine the amount of  $\text{Fe}^{2+}$  ions in the solution. The ore solution prepared above contains some iron in the  $\text{Fe}^{3+}$  state also. So, in determining total iron, all the ferric should first be brought to the ferrous state. The following reducing methods may be used:



*Method 1-Reduction with stannous chloride*

This method is used when the resulting solution can be titrated in presence of  $\text{HCl}$ , e.g., titration with  $\text{K}_2\text{Cr}_2\text{O}_7$ .

To a hot solution of iron ore, 3-4 N with respect to  $\text{HCl}$ , concentrated  $\text{SnCl}_2$  solution is added in slight excess to ensure complete reduction of  $\text{Fe}^{3+}$  to  $\text{Fe}^{2+}$ :



The solution is then cooled and the slight excess of  $\text{SnCl}_2$  is removed by adding a saturated solution of  $\text{HgCl}_2$ .



A slight silky precipitate of  $\text{Hg}_2\text{Cl}_2$  in the suspended form does not interfere to any significant extent.

**6.1.1 Determination of the amount of  $\text{Fe}^{2+}$  and Total Iron in the iron ore solution by  $\text{K}_2\text{Cr}_2\text{O}_7$**

*Reagents Required*




1. Standard potassium dichromate solution (N/10)
2. Stannous chloride solution (5%)



3. Mercuric chloride solution (saturated)
4. Sodium diphenylamine sulphonate indicator solution
5. Syrupy phosphoric acid
6. Concentrated sulphuric acid
7. Concentrated hydrochloric acid

### Theory

A known volume of the iron ore solution is titrated directly with standard  $K_2Cr_2O_7$  solution in a medium acidified with  $H_2SO_4$  (or  $HCl$ ) and  $H_3PO_4$  using sodium diphenylamine sulphonate as internal indicator :



First permanent appearance of violet-blue colouration indicates the end-point and the volume of  $K_2Cr_2O_7$  solution used corresponds to  $Fe^{2+}$  ions in the solution.

For determining total iron, another suitable aliquot of the iron ore solution is first reduced by the  $SnCl_2$  method and the total iron (which is now present as  $Fe^{2+}$ ) is determined with standard  $K_2Cr_2O_7$ .

### Procedure

#### (i) Determination of $Fe^{2+}$

With a pipet, transfer 50 ml of the iron ore solution to a titration flask. Add about 10 ml of dil.  $H_2SO_4$  and 6-8 drops of sodium diphenylamine sulphonate indicator solution. Titrate with standard  $K_2Cr_2O_7$  solution. When the colour of the solution changes to dark green, add 5 ml of syrupy phosphoric acid and continue titration until the colour changes to violet-blue. Take concordant readings.

#### (ii) Determination of Total Iron

With a pipet, transfer 20 ml of the iron ore solution to a titration flask. Add 5 ml of concentrated  $HCl$  and heat just to boiling. Add dropwise a 5% solution of  $SnCl_2$  (in 1:1  $HCl$ ) with thorough shaking of the flask until the yellow colour due to  $FeCl_3$  has given way to a faint green colour. Add 3-4 drops of  $SnCl_2$  in excess to ensure complete reduction. Now cool the flask rapidly under tap and with a test tube add about 5 ml of a saturated solution of  $HgCl_2$  in one lot and mix thoroughly. After 2 minutes, add 5 ml of syrupy phosphoric acid, 6-8 drops of the indicator solution and titrate rapidly with standard  $K_2Cr_2O_7$  solution until there is a change of colour from deep green to violet blue. Take concordant readings.



*Precautions*

1.  $\text{SnCl}_2$  solution should be added dropwise and should be thoroughly mixed after each addition.
2.  $\text{HgCl}_2$  solution should be added to the cooled solution in one lot and not drop by drop.
3. The reaction between  $\text{SnCl}_2$  and  $\text{HgCl}_2$  being slow, 2-3 minutes should be allowed for its completion.
4. If on addition of  $\text{HgCl}_2$ ,
  - (a) no precipitate appears,
  - (b) precipitate is heavy, crystalline and settles at the bottom of the flask, or
  - (c) a grey or black colour of elemental Hg appears,
 the solution should be discarded and reduction should be repeated.

*Observations and Calculations*

Weight of iron ore taken = w g  
 Volume of iron ore solution prepared = 250 ml

*Determination of  $\text{Fe}^{2+}$* 

Volume of iron ore solution taken for each titration = 50 ml  
 Volume of  $\text{N}/10 \text{ K}_2\text{Cr}_2\text{O}_7$  used = A ml  

$$\begin{array}{ccc} N_1 V_1 & = & N_2 V_2 \\ (\text{Fe}^{2+} \text{ solution}) & & (\text{K}_2\text{Cr}_2\text{O}_7) \\ N_1 \times 50 & = & \frac{1}{10} \times A \\ \text{or} \quad N_1 & = & \frac{A}{10 \times 50} \end{array}$$

Amount of  $\text{Fe}^{2+}$  per litre of iron ore solution =  $\frac{A \times 56}{10 \times 50}$  g

$$\begin{aligned} \% \text{ Fe}^{2+} \text{ in the ore} &= \frac{A \times 56}{10 \times 50} \times \frac{250}{1000} \times \frac{100}{w} \\ &= \frac{A \times 2.8}{w} \end{aligned}$$

*Determination of Total Iron*

Volume of iron ore solution taken for each titration = 20 ml  
 Volume of  $\text{N}/10 \text{ K}_2\text{Cr}_2\text{O}_7$  used = B ml



$$\begin{aligned}
 N_1 V_1 &= N_2 V_2 \\
 (\text{Iron}) & \quad (\text{K}_2\text{Cr}_2\text{O}_7) \\
 N_1 \times 20 &= \frac{1}{10} \times B \\
 \text{or } N_1 &= \frac{B}{10 \times 20}
 \end{aligned}$$

$$\text{Amount of iron per litre of the ore solution} = \frac{B \times 56}{10 \times 20} \text{ g}$$

$$\begin{aligned}
 \text{Therefore \% iron in the ore} &= \frac{B \times 56}{10 \times 20} \times \frac{250}{1000} \times \frac{100}{w} \text{ g} \\
 &= \frac{B \times 7}{w}
 \end{aligned}$$

### Exercises



155. What is the importance of grinding in the analysis of iron ore?
156. What is the purpose of roasting the ore before its dissolution in acid?
157. Why is it necessary to add only a very small excess of  $\text{SnCl}_2$  during the reduction of  $\text{Fe}^{3+}$ ?
158. What happens if the  $\text{HgCl}_2$  solution is added
  - (a) when the solution is still hot,
  - (b) drop by drop, or
  - (c) it is not added in sufficient amount?
159. Why is the solution cooled immediately after the reduction is complete?
160. No precipitate is formed on adding  $\text{HgCl}_2$  to an iron ore solution reduced with  $\text{SnCl}_2$ . What does it indicate?
161. What is the function of adding  $\text{H}_3\text{PO}_4$  during the titration?
162. What is meant by Internal Indicator, External Indicator and Self Indicator? Give one example of each.
163. Name the external indicator used in the titration of  $\text{Fe}^{3+}$  ions with  $\text{K}_2\text{Cr}_2\text{O}_7$ . How is the indicator solution prepared?
164. Describe the detection of the end-point with this indicator.
165. What important precautions should be observed with the use of  $\text{K}_3[\text{Fe}(\text{CN})_6]$  as external indicator?
166. Why has the external indicator method been largely replaced with internal indicator methods?
167. What will happen if  $\text{K}_3[\text{Fe}(\text{CN})_6]$  indicator is added to the titration flask?

### Method II: Reduction with Zn and $\text{dil. H}_2\text{SO}_4$



This method is normally used when the resulting solution is to be titrated with  $\text{KMnO}_4$ . A known volume of the iron ore solution prepared in  $\text{H}_2\text{SO}_4$  is taken in a conical flask and more acid is added to make the solution




about 4 N with respect to  $\text{H}_2\text{SO}_4$ . Granulated zinc or zinc dust is added which reacts with  $\text{H}_2\text{SO}_4$  to produce nascent hydrogen:



The nascent hydrogen so produced reduces  $\text{Fe}^{3+}$  to  $\text{Fe}^{2+}$ ,



Complete conversion of  $\text{Fe}^{3+}$  to  $\text{Fe}^{2+}$  is tested using KSCN or  $\text{NH}_4\text{SCN}$  solution as external indicator which produces blood red colour with  $\text{Fe}^{3+}$  ion:



The non-appearance of red colour indicates absence of  $\text{Fe}^{3+}$ . After the reduction is complete, excess zinc is removed either by filtration or by boiling until the whole of zinc dissolves.


#### 6.1.2 Determination of the amount of Iron in the iron ore solution by $\text{KMnO}_4$

##### Reagents Required

1. Standard potassium permanganate solution (N/10)
2. Copper sulphate solution
3. Ammonium thiocyanate solution
4. Dilute sulphuric acid
5. Granulated zinc or zinc dust.

##### Theory

A known volume of the iron ore solution prepared in  $\text{H}_2\text{SO}_4$  is reduced with Zn and  $\text{H}_2\text{SO}_4$  as described above. After the removal of excess of zinc, the solution is diluted to a definite volume. A suitable aliquot of this solution is then titrated with standard  $\text{KMnO}_4$  solution:



$\text{KMnO}_4$  acts as self indicator and appearance of light pink colour shows the end-point.



*Procedure*

With a pipet, transfer 50 ml of the iron ore solution (prepared in  $\text{H}_2\text{SO}_4$ ) to a conical flask. Add about 5 g of AR granulated zinc and 2 to 3 drops of copper sulphate solution. Place a short funnel in the mouth of the flask and add about 25 ml of dilute  $\text{H}_2\text{SO}_4$  (6-8 N). Slightly warm and allow the reaction to continue, with occasional shaking, until the solution appears pale green. Remove a drop of the reaction mixture with a glass rod and mix it with a drop of  $\text{NH}_4\text{SCN}$  solution placed on a white glazed tile. If a blood red colour appears (which indicates that reduction is incomplete), allow the reduction to proceed until a drop of the reaction mixture when mixed with a drop of  $\text{NH}_4\text{SCN}$  does not give a red colour ( $\text{Fe}^{2+}$  ions give only a faint pink tint with  $\text{NH}_4\text{SCN}$ ). Now filter the solution through a plug of glass wool placed in the neck of a funnel into a 100-ml measuring flask. (Alternatively, filter under suction through a gooch crucible with an asbestos fibre bed). Rinse the conical flask 2-3 times with 5-ml portions of dilute  $\text{H}_2\text{SO}_4$  and pass the same through the filter. Make the volume upto the mark with distilled water.

Pipet out 20 ml of this solution into a titration flask, add about 5 ml of dilute  $\text{H}_2\text{SO}_4$  and titrate against standard  $\text{KMnO}_4$  solution until a light pink colour appears in the reaction mixture. Take concordant readings.

*Precautions*

- (1) All the zinc used for reduction should be removed before titration. If zinc dust has been used for reduction, it is better to boil the solution to completely dissolve the zinc.
- (2) After the reduction is complete, the determination should be made as quickly as possible to avoid atmospheric oxidation of  $\text{Fe}^{2+}$  to  $\text{Fe}^{3+}$ .

*Observations and Calculations*

Weight of iron ore taken	= w g
Volume of iron ore solution prepared	= 250 ml
Volume of ore solution taken	= 50 ml
Volume made after reduction	= 100 ml
Volume of reduced solution taken for each titration	= 20 ml
Volume of N/10 $\text{KMnO}_4$ used	= C ml
100 ml reduced solution	= 50 ml iron ore solution
1 ml " "	= $\frac{50}{100}$ " " "
20 ml " "	= $\frac{50 \times 20}{100}$ " " "
	= 10 ml



$$N_1 V_1 = N_2 V_2$$

(Iron ore solution)                      (KMnO<sub>4</sub>)

$$N_1 \times 10 = \frac{1}{10} \times C$$

$$\text{or } N_1 = \frac{C}{10 \times 10}$$

$$\begin{array}{l} \text{Amount of total iron per} \\ \text{litre of the ore solution} \end{array} = \frac{C}{10 \times 10} \times 56 \text{ g}$$

$$\begin{aligned} \% \text{ of iron in the ore} &= \frac{C \times 56}{10 \times 10} \times \frac{250}{1000} \times \frac{100}{w} \\ &= \frac{C \times 14}{w} \end{aligned}$$

### Exercises

168. During reduction with Zn and H<sub>2</sub>SO<sub>4</sub>, why is a small funnel placed in the mouth of the flask?
169. What is the function of a few drops of copper sulphate solution added during reduction?
170. Can Fe<sup>3+</sup> ions be determined with KMnO<sub>4</sub> in presence of HCl? If not, why?
171. An iron ore has been dissolved in HCl. What procedure should be adopted to remove the interference of HCl in the determination of total iron by KMnO<sub>4</sub>?
172. Reduction with Zn and H<sub>2</sub>SO<sub>4</sub> has largely been replaced with that using zinc amalgam. Why?
173. How is zinc amalgam prepared?
174. List some other reagents that are used for the reduction of Fe<sup>3+</sup> to Fe<sup>2+</sup> during the determination of total iron in iron ore solution.

### 6.2 Copper Ore and Brass

Copper occurs both in the native form and in the combined state. The common ores are:

- |                       |   |
|-----------------------|---|
| (a) Cuprite (red)     | Cu <sub>2</sub> O                       |
| (b) Malachite (green) | Cu(OH) <sub>2</sub> ·CuCO <sub>3</sub>  |
| (c) Azurite (blue)    | Cu(OH) <sub>2</sub> ·2CuCO <sub>3</sub> |
| (d) Copper glance     | Cu <sub>2</sub> S                       |
| (e) Copper pyrites    | CuFeS <sub>2</sub>                      |



In addition to iron, metals like As, Sb, Zn, Ni, etc., bitumen and silica may be present as impurities.

#### *Preparation of Solution of the Ore*

About 1 g of the finely ground copper ore is taken in a beaker and warmed with 15-20 ml of concentrated  $\text{HNO}_3$  until the copper passes into solution. It is then evaporated on a hot plate to a volume of about 5 ml and after adding about 10 ml of concentrated  $\text{HCl}$  and an equal volume of 1:1  $\text{H}_2\text{SO}_4$ , it is again evaporated until dense white fumes of  $\text{SO}_3$  appear, indicating complete removal of nitrogen oxides. About 15 ml of distilled water followed by an equal volume of saturated bromine solution is then added and the mixture is heated. This ensures complete oxidation of any As and Sb to the pentavalent state. Excess of bromine is then boiled off. (if any blackish particles are seen in the solution, it may be sand which should be filtered.) The resulting solution which, in addition to  $\text{Cu}^{2+}$ , may contain  $\text{Fe}^{3+}$ ,  $\text{As}^{5+}$ ,  $\text{Sb}^{5+}$ ,  $\text{Zn}^{2+}$ , and  $\text{Ni}^{2+}$ , as impurities is diluted to 100 ml in a measuring flask.

#### *Brass*

The alloy brass consists mainly of copper and zinc but may contain small amounts of tin, lead and iron. A known weight of the sample (as drillings or turnings) is heated with concentrated  $\text{HNO}_3$  when copper, zinc, lead and iron pass into the solution while tin is precipitated as metastannic acid ( $\text{SnO}_2 \cdot \text{H}_2\text{O}$ ) which is filtered, dried, ignited and weighed to get the percentage of tin in the alloy. The filtrate is evaporated with concentrated  $\text{H}_2\text{SO}_4$  which expels nitrogen oxides. The residue is treated with distilled water and filtered. The precipitate is washed, dried, ignited and weighed as  $\text{PbSO}_4$  from which percentage of lead in brass is calculated. The filtrate which may contain  $\text{Fe}^{3+}$  and  $\text{Zn}^{2+}$  in addition to  $\text{Cu}^{2+}$  is diluted to 100 ml in a measuring flask.

#### 6.2.1 *Determination of the amount of Copper in a solution of copper ore or brass*



##### *Reagents Required*

1. Standard copper sulphate solution (N/10)
2. Sodium thiosulphate solution (N/10)
3. Ammonium thiocyanate solution (10%)
4. Dilute acetic acid
5. 1:1 ammonia solution
6. Freshly prepared starch solution
7. Sodium carbonate solution
8. Potassium iodide
9. Ammonium bifluoride.






*Theory*

When an excess of KI is added to a solution containing  $\text{Cu}^{2+}$  in neutral or slightly acidic medium, quantitative liberation of iodine takes place:





White precipitate


The liberated iodine is titrated with standard  $\text{Na}_2\text{S}_2\text{O}_3$  solution using freshly prepared starch solution as indicator near the end-point:



In the absence of  $\text{Fe}^{3+}$  (test with  $\text{NH}_4\text{SCN}$ ), the mineral acid is neutralised by dropwise addition of a solution of  $\text{Na}_2\text{CO}_3$  until a slight precipitate or turbidity appears:




The turbidity is removed by dropwise addition of dilute  $\text{CH}_3\text{COOH}$




and this adjusts the pH to a value at which As(V) and Sb(V) do not interfere.

When  $\text{Fe}^{3+}$  is present, dilute  $\text{NH}_3$  solution is added to precipitate it:



Ammonium bifluoride is then added which complexes iron and also



adjusts the pH to above 3.2 where As(V) and Sb(V) do not interfere.

*Procedure*(a) *Standardisation of sodium thiosulphate solution*

Pipet out 20 ml of N/10 copper sulphate solution into an iodine titration flask. Add 1 g of AR KI dissolved in 10 ml of distilled water. Stopper the flask, mix the contents and keep in dark for 1-2 minutes. Titrate against



standard  $\text{Na}_2\text{S}_2\text{O}_3$  solution. When the colour of the reaction mixture is straw yellow, add 2 ml of freshly prepared starch solution, mix and continue titration until the blue colour becomes faint. Add 10 ml of thiocyanate solution (10%  $\text{NH}_4\text{SCN}$  or  $\text{KSCN}$ ). An intense blue colour appears. Immediately titrate further to the complete disappearance of blue colour. Repeat to get concordant readings.

(b) *Estimation of copper*

(i) *When  $\text{Fe}^{3+}$  is absent* (Test with  $\text{NH}_4\text{SCN}$ )

Pipet out 20 ml of ore or brass solution into an iodine titration flask. Add  $\text{Na}_2\text{CO}_3$  solution dropwise with shaking until a slight turbidity appears in the solution. Add dilute  $\text{CH}_3\text{COOH}$  dropwise until the turbidity just disappears and the solution becomes clear. Add 1 g of AR KI dissolved in 10 ml of distilled water and proceed as in (a) above.

(ii) *When  $\text{Fe}^{3+}$  is present*

Pipet out 20 ml of the ore or alloy solution into an iodine titration flask. Add 1:1 ammonia solution dropwise with shaking until the solution smells faintly of ammonia. To dissolve the precipitated  $\text{Fe}(\text{OH})_3$ , add 2 g of  $\text{NH}_4\text{HF}_2$  and shake. Add 1 g of AR KI dissolved in 10 ml of distilled water and proceed as in (a) above.

*Precautions*

- (1) When much of bitumen or sulphur is present, the ore should be roasted before treating with acid.
- (2) Brass surface, if not clean, should be washed with ether and then dried in air.
- (3) Large excess of ammonia or  $\text{Na}_2\text{CO}_3$  and  $\text{CH}_3\text{COOH}$ , as the case may be, should be avoided.
- (4) Direct sunlight should be avoided as it catalyses atmospheric oxidation of I
- (5) After addition of thiocyanate solution, the titration should not be delayed.

*Observations and Calculations*

(a) *Standardisation of thiosulphate solution*

Volume of N/10  $\text{CuSO}_4 \cdot 5\text{H}_2\text{O}$  solution taken = 20 ml

Let the concordant volume of  $\text{Na}_2\text{S}_2\text{O}_3$  solution used = A ml

$$N_1 V_1 = N_2 V_2$$

(Copper sulphate) ( $\text{Na}_2\text{S}_2\text{O}_3$ )

$$\frac{1}{10} \times 20 = N_2 \times A$$



$$\text{Therefore, } N_2 = \frac{1}{10} \times 20 \times \frac{1}{A} = \frac{2}{A}$$

(Normality of  $\text{Na}_2\text{S}_2\text{O}_3$ )

(b) *Estimation of copper*

Let the weight of ore or alloy taken	= w g
Volume of solution prepared	= 100 ml
Volume taken for each titration	= 20 ml
Let the concordant volume of $\text{Na}_2\text{S}_2\text{O}_3$ used	= B ml
$N_1 V_1$ (copper)	$= N_2 V_2$ ( $\text{Na}_2\text{S}_2\text{O}_3$ )
$N_1 \times 20$	$= \frac{2}{A} \times B$
or $N_1$	$= \frac{2}{A} \times \frac{B}{20} = \frac{B}{10 A}$

Amount of copper per litre of the ore or alloy solution	$= \frac{B \times 63.5}{10 A} \text{ g}$
---	--

Therefore, % of copper in ore or alloy	$= \frac{B \times 63.5 \times 100 \times 100}{10 A \times 1000 \times w}$
	$= \frac{B \times 63.5}{A \times w}$

**Exercises**

175. Why is it necessary to oxidise arsenic and antimony to the pentavalent state?
176. Why is it necessary to remove nitrite and nitrogen oxides?
177. Describe some methods, other than evaporating the solution with  $\text{H}_2\text{SO}_4$ , for removing nitrite and nitrogen oxides from the solution.
178. How does iron interfere in the copper estimation?
179. Name some reagent, other than ammonium bifluoride, which can complex  $\text{Fe}^{3+}$  and prevent its reaction with  $\Gamma^-$ .
180. Name the factors that catalyse atmospheric oxidation of  $\Gamma^-$  ion.
181. What is the effect of low pH on the copper estimation?
182. On adding KI to the  $\text{Cu}^{2+}$  solution, a brown precipitate is seen. What is it due to?
183. Why is thiocyanate solution added towards the end-point of the titration?
184. During the titration of  $\text{I}_2$  with thiosulphate, it is sometimes seen that at the end-point, the blue colour appears again and again. Explain.



### 6.3 Silver Ore and Silver Alloy

Silver coins or other commercially available silver alloys may contain varying amounts of zinc and nickel in addition to silver and copper. The silver content of the alloy determines its value and characteristics.

#### *Preparation of the solution*

The surface of the alloy (in the form of a wire, thin sheet or coin) is cleaned by rubbing with emery cloth and subsequently washed with dry acetone to free it of grease. The alloy is then cut into pieces and 0.4-0.5 g (accurately weighed) of it is placed in a conical flask. Through a small funnel, placed in the mouth of the flask to avoid mechanical loss, 10-15 ml of dilute  $\text{HNO}_3$  (1:1) is added. The flask is warmed gently on a water bath or a low-temperature hot plate until the alloy is completely dissolved. The solution is now boiled for 5-10 minutes to expel lower nitrogen oxides. The solution is cooled, transferred quantitatively to a 100-ml measuring flask—washing the conical flask and funnel with distilled water into the measuring flask—and made up to the mark.

*The Ores*, silver glance ( $\text{Ag}_2\text{S}$ ) and copper-silver glance ( $\text{Ag}_2\text{S} \cdot \text{Cu}_2\text{S}$ ) can be similarly brought into solution by treating with nitric acid followed by filtration.


#### 6.3.1 *Determination of the amount of Silver in a solution of silver ore or alloy*

##### *Reagents Required*


1. Standard silver nitrate solution (N/20)
2. Potassium thiocyanate solution (N/20)
3. Ferric alum indicator solution
4. Dilute  $\text{HNO}_3$ .

##### *Theory*

Silver ions in a solution containing free nitric acid can be titrated with a standard solution of  $\text{KSCN}$  or  $\text{NH}_4\text{SCN}$  using a solution of ferric alum or ferric nitrate as indicator (Volhard method). When thiocyanate solution is added, a white precipitate of silver thiocyanate results:



After the whole of  $\text{Ag}^+$  ions are precipitated, a slight excess of thiocyanate reacts with  $\text{Fe}^{3+}$  ions to produce a red colour.





*Procedure*(a) *Standardisation of thiocyanate solution*

Pipet out 20 ml of standard N/20  $\text{AgNO}_3$  solution into a titration flask and add 5 ml of dilute  $\text{HNO}_3$  and 1 ml of ferric alum indicator. Titrate against KSCN solution until a permanent faint reddish-brown colour appears. Repeat to get concordant readings.

(b) *Estimation of silver in the alloy or ore solution*

Repeat the above procedure taking 20 ml of the silver alloy or ore solution and get concordant readings.

*Precautions*

1. All the apparatus should be washed with distilled water.
2. Nitric acid must be free of the lower oxides of nitrogen.
3. Near the end-point, the titration must be carried out very slowly and with constant shaking.

*Observations and Calculations*

Weight of silver alloy (or ore) dissolved = w g

Volume of the alloy (or ore) solution prepared = 100 ml

(a) *Standardisation of KSCN solution*

Volume of standard N/20  $\text{AgNO}_3$  taken = 20 ml

Volume of KSCN solution used = A ml

$$\begin{array}{ccc} N_1 V_1 & = & N_2 V_2 \\ \text{(KSCN)} & & \text{(N/20 AgNO}_3\text{)} \end{array}$$

$$N_1 \times A = \frac{1}{20} \times 20$$

$$\text{Therefore, } N_1, \text{ normality of KSCN solution} = \frac{1}{A}$$

(b) *Estimation of silver in the solution*

Volume of silver alloy (or ore) solution taken = 20 ml

Volume of KSCN solution used = B ml

$$\begin{array}{ccc} N_1 V_1 & = & N_2 V_2 \\ \text{(KSCN)} & & \text{(Silver solution)} \end{array}$$

$$\frac{1}{A} \times B = N_2 \times 20$$



$$\text{Therefore, } N_2, \text{ normality of silver solution} = \frac{B}{A \times 20}$$

$$\text{Strength of silver solution} = \frac{B}{A \times 20} \times 108 \text{ g/l}$$

$$\begin{aligned} \text{Therefore, percentage of silver in the alloy or the ore} &= \frac{B \times 108}{A \times 20} \times \frac{100}{1000} \times \frac{1}{w} \times 100 \\ &= \frac{B}{A} \times \frac{54}{w} = \frac{54B}{A.w} \end{aligned}$$

### Exercises

185. Why is it necessary to avoid the use of tap water?
186. What is the function of nitric acid in the titration?
187. Why is it necessary to remove the lower oxides of nitrogen from nitric acid?
188. How is nitrous acid removed from nitric acid solution?
189. How is approach of the end-point detected?
190. Why is it necessary to shake the reaction mixture vigorously near the end-point?

### 6.4 Pyrolusite

Manganese does not occur free in nature. Its most commonly found ore is Pyrolusite ( $\text{MnO}_2$ ) which sometimes contains small amounts of Brounite ( $\text{Mn}_2\text{O}_3$ ), Manganite [ $\text{Mn}_2\text{O}_3 \cdot \text{H}_2\text{O}$  or  $\text{MnO}(\text{OH})$ ], Hausmanite ( $\text{Mn}_3\text{O}_4$ ) and/or some other impurities. When the ore is to be used for metallurgical purposes (i.e., as a source of Manganese metal or for the production of ferromanganese), it is graded on the basis of its manganese content which can be determined by dissolving the ore in nitric acid and oxidising manganese to permanganic acid using sodium bismuthate ( $\text{NaBiO}_3$ ). After filtering off the excess of the bismuthate, the permanganic acid is determined with a standard ferrous ion solution.


Being an efficient oxidising agent, pyrolusite is directly put to several industrial uses such as:

- (i) Production of  $\text{Cl}_2$  by the action of conc.  $\text{HCl}$  (Weldon process)
- (ii) A drier in paints.
- (iii) A depolariser in Leclanche cell and Dry cell
- (iv) Bleaching agent
- (v) A catalyst in the preparation of oxygen by heating potassium chlorate ( $\text{KClO}_3$ ).

For these purposes, the ore is graded on the basis of its oxidising capacity which is reported in terms of the percentage of 'Available Oxygen' in pyrolusite.



Available oxygen of pyrolusite is that part of oxygen which is available for oxidation of a reducing agent when the ore is treated with a strong acid:




#### 6.4.1 Determination of Available Oxygen in Pyrolusite iodometrically Reagents Required


1. Standard sodium thiosulphate solution (N/10)
2. Potassium iodide solution (5%)
3. Freshly prepared starch solution
4. Conc. HCl.

#### Theory



A known weight of dry ore is heated with conc. HCl. Chlorine equivalent to available oxygen is liberated as per the following equation:




or



The chlorine gas thus evolved is passed into a solution of KI when an equivalent amount of iodine is liberated



which is titrated with a standard solution of sodium thiosulphate using starch solution as indicator near the end-point.



The amount of thiosulphate consumed corresponds to the oxygen available from pyrolusite.

#### Procedure

Set up the apparatus as shown in Figure 12. Place about 100 ml of a 5% solution of KI (A.R. Grade) in the conical flask (A). Weigh accurately the sample bottle containing the finely pulverised and dry pyrolusite ore. Transfer



about 0.5 g of the sample to the distillation flask D and weigh the bottle again. Add about 30 ml of conc. HCl to the flask. Heat the distillation flask gently and from a Kipp's apparatus, pass a slow and steady stream of  $\text{CO}_2$  into the contents of the distillation flask. After the ore has completely dissolved, raise the temperature and boil the contents for about 10 minutes. Now disconnect the delivery tube (C) from the distillation flask and transfer the contents of the conical flask into a 250-ml measuring flask. Rinse the conical flask, the delivery tube and the guard tube with KI solution into the measuring flask and make up the volume upto the mark. Transfer 50 ml of this solution into a conical flask and titrate against  $\text{N}/10 \text{ Na}_2\text{S}_2\text{O}_3$ . When the colour of the solution turns straw yellow, add about 2 ml of freshly prepared starch solution and titrate further till the blue colour just disappears. Take concordant readings.




Fig. 12 Determination of Pyrolusite.

- |                 |                      |
|-----------------|----------------------|
| A—Conical flask | B—Burner             |
| C—Delivery tube | D—Distillation flask |
| G—Guard tube    |                      |

### Observations and Calculations

Initial weight of sample bottle =  $w_1$  g

Final " " " =  $w_2$  g

Therefore, Weight of pyrolusite sample taken =  $(w_1 - w_2)$  g

Total volume of iodine solution prepared = 250 ml

Volume taken for each titration = 50 ml



Let the concordant volume of N/10  $\text{Na}_2\text{S}_2\text{O}_3$  used = A ml

Then  $N_1 V_1$  =  $N_2 V_2$   
(Iodine solution) (N/10  $\text{Na}_2\text{S}_2\text{O}_3$ )

$$N_1 \times 50 = \frac{1}{10} \times A$$

$$\text{or } N_1 = \frac{A}{10 \times 50}$$

(i) Strength of iodine solution in terms of  $\text{MnO}_2$  =  $\frac{A}{10 \times 50} \times 43.47 \text{ g/l}$

or weight of  $\text{MnO}_2$  in  $(w_1 - w_2)$  g of pyrolusite =  $\frac{A}{10 \times 50} \times \frac{43.47 \times 250}{1000} \text{ g}$

Therefore, % of  $\text{MnO}_2$  in pyrolusite =  $\frac{A \times 43.47 \times 250}{10 \times 50 \times 1000} \times \frac{100}{w_1 - w_2}$   
=  $\frac{A \times 43.47}{20 \times (w_1 - w_2)}$

(ii) Strength of iodine solution in terms of available oxygen =  $\frac{A \times 8}{10 \times 50} \text{ g/l}$

Weight of oxygen available from  $(w_1 - w_2)$  g pyrolusite =  $\frac{A \times 8}{10 \times 50} \times \frac{250}{1000} \text{ g}$

% Available oxygen =  $\frac{A \times 8}{10 \times 50} \times \frac{250}{1000} \times \frac{100}{w_1 - w_2}$   
=  $\frac{A \times 8}{20 \times (w_1 - w_2)}$

(iii) Similarly, weight of  $\text{Cl}_2$  that can be prepared from  $(w_1 - w_2)$  g pyrolusite =  $\frac{A \times 35.5}{10 \times 50} \times \frac{250}{1000} \text{ g}$

or Weight of  $\text{Cl}_2$  obtainable from 100 g of pyrolusite =  $\frac{A \times 35.5}{10 \times 50} \times \frac{250}{1000} \times \frac{100}{w_1 - w_2} \text{ g}$   
=  $\frac{A \times 35.5}{20 \times (w_1 - w_2)} \text{ g}$

### Precautions

(1) To ensure complete and rapid decomposition of the ore by conc.  $\text{HCl}$ ,



it should be finely powdered in an agate mortar.

(2) To avoid the absorption of moisture by the powdered ore, it should be immediately transferred to a small stoppered weighing bottle.

(3) To make the apparatus airtight, all connections should be made with ground glass joints.

(4)  $\text{CO}_2$  should be passed at a very slow rate otherwise some iodine might be lost from the solution.

(5) Before discontinuing heating at the end, disconnect the delivery tube to avoid back-suction of the absorption solution.




### Exercises

191. Why is a stream of  $\text{CO}_2$  passed through the decomposing mixture?
192. What are the contents of the guard tube? What is its function?
193. Why is the conical flask kept immersed in ice-water?
194. What is the use of Pyrolusite in glass industry?
195. In what physical state does Pyrolusite occur in nature?


### 6.4.2 Determination of Available Oxygen in Pyrolusite by $\text{KMnO}_4$

#### Theory



A known weight of the pyrolusite sample is treated with a known excess of an acidified solution of a reducing agent, such as (a) ferrous sulphate, (b) sodium oxalate, or (c) sodium arsenite. An equivalent amount of the reducing agent is oxidised as per the following reactions:



The excess of the reducing agent is determined by titrating with a standard solution of  $\text{KMnO}_4$ , which itself acts as indicator:







### Procedure (With sodium oxalate)

#### Reagents Required

1. Standard sodium oxalate solution (N/10)
2. Standard potassium permanganate solution (N/10)
3.  $\text{H}_2\text{SO}_4$  (10%).

Take two 250-ml conical flasks. Add the following reagents to each:

- (i) About 0.1-0.15 g finely pulverised, dry and accurately weighed (by difference method using a weighing bottle) pyrolusite sample
- (ii) 40 ml of standard N/10 sodium oxalate solution (with a pipet)
- (iii) 40 ml of approximately 10%  $\text{H}_2\text{SO}_4$  (with a measuring cylinder).

Place a small funnel in the mouth of each flask and keep them on a hot plate. Boil the contents gently until no black particles are visible in the flasks. Dilute the resultant dirty solution (usually milky) to about 100 ml and titrate slowly with N/10  $\text{KMnO}_4$  solution until a light pink colour appears. The amount of sodium oxalate consumed by pyrolusite is a measure of  $\text{MnO}_2$  or available oxygen.

#### Precautions

- (1) Due to presence of impurities, the solution after boiling may sometimes be coloured brown which interferes with the end-point. In such a case, the solution should be filtered before use.
- (2) During boiling, the concentration of  $\text{H}_2\text{SO}_4$  should not exceed 20% otherwise it may lead to decomposition of oxalic acid into CO and  $\text{CO}_2$ . To avoid this, some water may be added to the flask during boiling to make up for the loss.

#### Observations and Calculations

Flask A—	Weight of sample	= $w_A$ g
	Volume of N/10 sodium oxalate added	= 40 ml
	Let the volume of N/10 $\text{KMnO}_4$ consumed	= $V_A$ ml



Therefore, Volume of N/10 sodium oxalate used against

$$w_A \text{ g of pyrolusite} = (40 - V_A) \text{ ml}$$

$$\text{and weight of MnO}_2 \text{ in } w_A \text{ g of sample} = \frac{(40 - V_A) \times 43.47}{10 \times 1000} \text{ g}$$

$$\begin{aligned} \text{Therefore, } \% \text{ MnO}_2 &= \frac{(40 - V_A)}{10 \times 1000} \times \frac{43.47}{w_A} \times 100 \\ &= \frac{(40 - V_A) \times 43.47}{100 \times w_A} \end{aligned}$$

$$\text{and } \% \text{ available Oxygen} = \frac{(40 - V_A) \times 8}{100 \times w_A} = O_A$$

$$\text{Flask B— Weight of the sample} = w_B \text{ g}$$

$$\text{Volume of N/10 sodium oxalate} = 40 \text{ ml}$$

$$\text{Let the volume of N/10 KMnO}_4 \text{ used} = V_B \text{ ml}$$

$$\text{Therefore, } \% \text{ MnO}_2 = \frac{(40 - V_B) \times 43.47}{100 \times w_B}$$

$$\text{and } \% \text{ available Oxygen} = \frac{(40 - V_B) \times 8}{100 \times w_B} = O_B$$

$$\text{Hence mean value of } \% \text{ Available Oxygen} = \frac{O_A + O_B}{2}$$

### Exercise

196. Which of the three reducing agents suggested, namely ferrous sulphate, sodium oxalate or sodium arsenite is better and why?



### 6.4.3 Determination of Available Oxygen in Pyrolusite by $\text{KIO}_3$ (Andrews titration)

#### Reagents Required


1. Standard potassium iodate solution (0.2N)
2. Potassium iodide solution (0.1 M)
3. Conc. HCl
4. Carbon tetrachloride.

#### Theory



In presence of a large excess of HCl,  $\text{MnO}_2$  can oxidise iodide to iodine monochloride, via the intermediate formation of iodine:











Thus the overall reaction may be written as





However, in presence of excess iodide, the reaction stops at the iodine stage (reaction 6.31). Thus, when to a known weight of the pyrolusite sample taken in a stoppered bottle is added a known excess of KI (titrated with standard  $\text{KIO}_3$ ) and the mixture is shaken in presence of a large excess of HCl, a part of iodide is oxidised by  $\text{MnO}_2$  present in the pyrolusite sample. The excess of KI is determined by titrating the resultant mixture (which may contain either  $\text{I}^-$  and  $\text{I}_2$  or  $\text{I}_2$  and  $\text{ICl}$ ) with the standard  $\text{KIO}_3$  in presence of chloroform or carbon tetrachloride when the iodide is first oxidised to  $\text{I}_2$ :



or



which is further converted to  $\text{ICl}$ :



The disappearance of the colour of iodine in the organic layer indicates the end-point. The result is calculated from the amount of KI taken and the amount left after reaction with pyrolusite.

#### Procedure

Transfer 0.15-0.2 g of finely powered pyrolusite sample to an iodine titration flask. Add 30 ml of about 0.1M solution of KI (AR) and 30 ml of conc. HCl. Stopper the flask and shake vigorously until the solid has dissolved. Now add about 5 ml of  $\text{CCl}_4$  and titrate with 0.05M (0.2N)  $\text{KIO}_3$  solution until there is no trace of violet colour of iodine in the carbon tetrachloride layer. Let the volume of  $\text{KIO}_3$  used be  $V_A$  ml.

**Blank** —In another flask, take 30 ml of the same KI solution and 30 ml conc. HCl. Add 5 ml of  $\text{CCl}_4$  and titrate with 0.05M  $\text{KIO}_3$  solution in the same way as before. Let the volume of  $\text{KIO}_3$  used be  $V_B$  ml.



*Precautions*

- (1) After each addition of  $\text{KIO}_3$  from the burette, the flask should be stoppered and shaken vigorously.
- (2) The concentration of  $\text{HCl}$  should never be less than 3.5-4N at the end-point.

*Observations and Calculations*

$$\begin{aligned}
 \text{Weight of sample taken} &= w \text{ g} \\
 \text{Volume of 0.2N } \text{KIO}_3 \text{ used in Blank} &= V_B \text{ ml} \\
 \text{Volume of 0.2N } \text{KIO}_3 \text{ used against sample} &= V_A \text{ ml} \\
 \text{Therefore, } \text{MnO}_2 \text{ in } w \text{ g sample} &\equiv (V_B - V_A) \text{ ml of 0.2 N solution} \\
 &= (V_B - V_A) \times 0.2 \times \frac{43.47}{1000} \text{ g} \\
 \% \text{ of } \text{MnO}_2 \text{ in sample} &= \frac{(V_B - V_A) \times 0.2 \times 43.47 \times 100}{1000 \times w} \\
 \% \text{ Available Oxygen} &= \frac{(V_B - V_A) \times 0.2 \times 8 \times 100}{1000 \times w} \\
 &= \frac{(V_B - V_A) \times 0.16}{w}
 \end{aligned}$$

**Exercises**

197. What is the equivalent weight of  $\text{KI}$  and  $\text{KIO}_3$  in the determination?
198. Why is vigorous shaking required during the titration?
199. What happens if the concentration of  $\text{HCl}$  is lower than that recommended?

**6.5 Calcium Carbonate Minerals**

Calcium carbonate occurs in nature in different forms—colourless, white to coloured materials and physical state being anything from a soft amorphous mass to hard rocks;

- (1) Dogtoothspar, Iceland spar, Nailhead spar and Salinspar are varieties of calcite crystal and used as phosphors. Iceland spar is transparent and used in optical instruments
- (2) *Marble* is also crystalline and is used for building, ornamental, monumental and statuary purposes: as chips, abrasive for soaps and for neutralisation of acids.
- (3) *Chalk* contains 90% calcite and may be soft, incoherent and porous to hard and crystalline. It is used for whiting, crayons, scouring and polishing preparations.
- (4) *Limestone* is most widely distributed and is the most important source



of  $\text{CaCO}_3$ . It usually contains  $\text{MgCO}_3$  in amounts which vary from traces to that present in Dolomite (containing  $\text{CaCO}_3$  and  $\text{MgCO}_3$  in equimolar amounts). Iron oxide, aluminium oxide, silica (free or combined as clay or feldspar) and sulphur (as pyrites,  $\text{FeS}_2$ , or gypsum,  $\text{CaSO}_4$ ) are other important minor constituents present in limestone and dolomite.


These minerals are used for a variety of purposes—building, whitening, manufacture of lime, portland and natural cements, fertiliser, soft glass, refractory material (dolomite), as a flux in various metallurgical processes, source of  $\text{CO}_2$ , railway ballast, macadam in lithography, cement concrete and asphalt concrete, in agriculture, as a solid diluent and carrier in pesticides (dolomite).

The value and suitability of the mineral for any particular commercial purpose depends on the physical state of the mineral and to a large extent on the amount of  $\text{CaCO}_3$ ,  $\text{MgCO}_3$  and the amounts and nature of other impurities, for which a complete analysis of the mineral will be ideal. For routine work, however, the analysis of limestone and dolomite includes the following determinations:

- (i) Available carbon dioxide
- (ii) Loss on ignition
- (iii) Impure silica or acid insoluble matter
- (iv) Combined oxides ( $\text{Al}_2\text{O}_3 + \text{Fe}_2\text{O}_3$ )
- (v)  $\text{CaO}$ , and
- (vi)  $\text{MgO}$ .

#### (i) Available Carbon Dioxide

A known weight of the powdered sample is decomposed by heating with syrupy phosphoric acid. Using a current of  $\text{CO}_2$ -free



air, the  $\text{CO}_2$  evolved from the sample is led through a water absorbent (anhydrous  $\text{CaSO}_4$ ) into weighed bulbs containing  $\text{KOH}$  solution. The increase in the weight of  $\text{KOH}$  bulbs gives the weight of  $\text{CO}_2$ . The percentage available  $\text{CO}_2$

$$= \frac{\text{Increase in the weight of KOH bulbs}}{\text{weight of sample taken}} \times 100 \quad (6.37)$$

#### (ii) Loss on Ignition

A weighed amount of the powdered air-dried sample, taken in a porcelain or platinum crucible, is dried at  $110^\circ\text{C}$  for 1 hour and the loss in weight, on percentage basis, is reported as superficially adsorbed moisture. The temperature of the crucible is then slowly raised to  $1000\text{--}1100^\circ\text{C}$  and the sample is ignited to constant weight. The percentage loss on ignition is a rough measure of the carbonate in the sample.





(iii) *Impure Silica or Acid Insoluble Matter*

It is determined by adding 1:1 HCl to about 1 g of the sample in a covered porcelain dish and heating on a water bath to dryness. The dry mass is then digested with 5-10 ml conc. HCl for about 5 minutes and diluted with distilled water. The resultant mixture is heated on a water bath for about 10 minutes and filtered using an ashless filter paper. The residue is washed with hot water, ignited along with the filter paper in a weighed silica crucible, cooled in a desiccator and weighed. The amount of the residue on percentage basis is reported as Impure Silica or Acid Insoluble Matter.

(iv) *Combined Oxides*

The combined filtrate and washings from the above determination are boiled with a few drops of conc.  $\text{HNO}_3$  (to convert any  $\text{Fe}^{2+}$  to  $\text{Fe}^{3+}$ ). About 1 g  $\text{NH}_4\text{Cl}$  is dissolved in the contents, followed by the addition of 2-3 drops of methyl red indicator. The solution is again heated to boiling and 1:1 ammonia solution added dropwise till the colour is just yellow. Boiling is continued for 2-3 minutes. Iron and aluminium are precipitated as hydroxides:



The precipitate is filtered, washed with hot water, dried and ignited [  $2\text{Fe}(\text{OH})_3 \rightarrow \text{Fe}_2\text{O}_3 + 3\text{H}_2\text{O}$ ,  $2\text{Al}(\text{OH})_3 \rightarrow \text{Al}_2\text{O}_3 + 3\text{H}_2\text{O}$  ] in a silica or platinum crucible to constant weight. The percentage of mixed

$$\text{oxides} = \frac{\text{Weight of residue}}{\text{Weight of sample taken}} \times 100 \quad (6.40)$$

(In addition to  $\text{Fe}_2\text{O}_3 + \text{Al}_2\text{O}_3$ , the residue may contain  $\text{TiO}_2$ ,  $\text{Mn}_3\text{O}_4$ ,  $\text{AlPO}_4$  and  $\text{FePO}_4$ ).


(v) *Calcium Oxide*6.5.1 *Determination of the amount of Calcium in Limestone**Reagents Required*

1. Standard potassium permanganate solution (N/10)
2. Ammonium oxalate solution (8%)
3. 1:1 ammonia solution
4. Dilute  $\text{H}_2\text{SO}_4$
5. Dilute HCl
6. Dilute  $\text{HNO}_3$
7. Silver nitrate solution
8. Methyl red indicator solution.




## Theory



Calcium in a solution of limestone or dolomite (from which acid insoluble matter and oxides of iron and aluminium have been removed) is precipitated as calcium oxalate by adding ammonium oxalate in a medium made slightly alkaline using ammonia:



The precipitate is filtered, washed free of oxalate and chloride ions, and dissolved in dilute sulphuric acid:



The oxalic acid liberated, which is equivalent to calcium in the original solution, is titrated with a standard solution of  $\text{KMnO}_4$ :



## Procedure

Add 2 drops of methyl red indicator to the combined filtrate and washings from the ammonia precipitation (removal of  $\text{Fe}_2\text{O}_3$  and  $\text{Al}_2\text{O}_3$ ) and acidify with dilute  $\text{HCl}$  (indicated by appearance of red colour). Reduce the volume to about 200 ml by evaporation. To the hot solution add slowly about 25 ml of a hot 8% ammonium oxalate solution with constant stirring with a glass rod (A slight precipitate appears due to the large excess of ammonium oxalate added). Add 1:1 ammonia solution dropwise until the red colour of the solution changes to yellow. Stir vigorously for 2-3 minutes and keep undisturbed for half an hour to let the precipitate settle down. Filter by decantation through a Whatman filter paper No. 40 (540). Wash the precipitate repeatedly with about 5-ml portions of 0.1% ammonium oxalate solution until the filtrate is free from chloride (filtrate does not give a precipitate with  $\text{AgNO}_3$  solution acidified with dilute  $\text{HNO}_3$ ). Then wash the precipitate with small amounts of cold distilled water until the filtrate is free from oxalate ion (filtrate does not decolourise hot very dilute  $\text{KMnO}_4$ ). Now place the funnel in the mouth of a 250-ml measuring flask, pierce a hole in



the filter paper with a glass rod and wash down the precipitate into the flask with warm distilled water. Pour some dilute  $\text{H}_2\text{SO}_4$  on the filter paper to dissolve any precipitate sticking to it. Now shake the flask to dissolve the precipitate (add more  $\text{H}_2\text{SO}_4$ , if necessary) and make up the volume upto the mark. Pipet out 50 ml of this solution into a titration flask, add about 10 ml of dilute  $\text{H}_2\text{SO}_4$ , heat to about  $60^\circ\text{C}$  and titrate with  $\text{N}/10 \text{ KMnO}_4$  solution until a light pink colour appears. Take concordant readings.

*Alternatively* dilute the combined filtrate and washings to a known volume (say 250 ml). Take 50 ml of this solution, precipitate calcium as oxalate, filter and wash free from chloride and oxalate, in a manner described above. Transfer the filter paper, along with the precipitate, to a titration flask, add 20 ml of dilute  $\text{H}_2\text{SO}_4$  and about the same volume of distilled water. Shake to dissolve the precipitate, warm to about  $60^\circ\text{C}$  and titrate with  $\text{N}/10 \text{ KMnO}_4$  solution.

#### Precautions

- (1) The washing liquid should always be taken in the beaker in which precipitation was carried out and then it should be transferred to the filter paper.
- (1) A fresh portion of the washing liquid should be used only when the first portion has completely passed through the filter paper.
- (3) For testing the filtrate for the presence of chloride or oxalate, a few drops of the filtrate should be collected directly from the funnel.
- (4) Any precipitate sticking to the filter paper may be loosened by forcing on it a jet of distilled water from a wash bottle.
- (5) Any precipitate sticking to the beaker after washing should be dissolved in dilute  $\text{H}_2\text{SO}_4$  and transferred to the measuring flask.

#### Observations and Calculations

Weight of the sample taken =  $w$  g

Volume of calcium ion/oxalate solution prepared = 250 ml

Volume taken for each titration = 50 ml

Let the concordant volume of  $\text{N}/10 \text{ KMnO}_4$  used =  $V$  ml

$$\begin{array}{ll} N_1 V_1 & = N_2 V_2 \\ \text{(Calcium)} & \text{(KMnO}_4\text{)} \end{array}$$

$$N_1 \times 50 = \frac{1}{10} \times V$$

$$\text{Therefore, } N_1 = \frac{V}{10 \times 50}$$

$$\text{Strength of calcium solution in terms of CaO} = \frac{V \times 28}{10 \times 50} \text{ g/l}$$



Weight of calcium (as CaO) in  $w$  g of the sample

$$= \frac{V \times 28}{10 \times 50} \times \frac{250}{1000} \text{ g}$$

% of calcium (as CaO) in the sample

$$= \frac{V \times 28}{10 \times 50} \times \frac{250}{1000} \times \frac{100}{w}$$

$$= \frac{V \times 1.4}{w}$$

### Exercises

200. Why is it necessary to wash the precipitate of calcium oxalate free of chloride and oxalate ions?
201. What improvement in the procedure is required for analysing dolomite, or limestones with higher magnesium content?
202. How is magnesium oxide determined in limestone or dolomite?




---

## Miscellaneous

### 7.1 Lime

Lime is a very important industrial material which is largely used for the manufacture of bleaching powder, glass, sulphite pulp, soda lime, calcium carbide, washing soda and caustic soda. It is also used for structural purposes (cement and mortar), for white washing, in textile industry, in sugar refining, for cooking rags in paper manufacture, for water softening, for tanning of leather, for preparation of  $\text{NH}_3$  and as a very good fertilizer for soil.

Lime is the product of calcination of lime stone:



There being several varieties of limestone, the limes prepared from them show corresponding variations in composition. The type of analysis required on a given sample depends to some extent on the use for which the sample is intended. Though routine analysis includes the same determinations as are carried out on limestone, there are certain specific uses which depend on the caustic value of lime (CaO content), and the impurities including  $\text{CaCO}_3$  are not available for reaction. It is therefore often desirable that available CaO content of lime be determined.


#### 7.1.1. *Determination of Available Lime or Free CaO in Industrial Lime or in Milk of Lime or Determination of Caustic Value of Agricultural Lime Iodimetrically*

##### *Reagents Required*

1. Standard iodine solution (N/10)
2. Standard sodium thiosulphate solution (N/10)
3. Freshly prepared starch solution.

##### *Theory*



A known weight of the powdered sample is slaked with boiling water when CaO content reacts:





A measured excess of iodine solution is then added when the base reacts



with iodine:



The excess of iodine is back-titrated with a standard  $Na_2S_2O_3$  solution using starch solution as indicator near the endpoint:



### Procedure

Transfer about 0.2 g of powdered and accurately weighed (by difference method) lime sample to an iodine titration flask. Add about 100 ml of boiled distilled water. Heat nearly to 60°C. Stopper the flask and shake vigorously for 5 minutes. Remove the stopper and boil for 5-10 minutes (in the analysis of milk of lime, use 10 ml of the sample and omit boiling). Cool and add 40 ml of standard N/10 iodine solution. Stopper the flask and shake until the whole of lime has dissolved. Titrate against N/10  $Na_2S_2O_3$  using starch solution as indicator. Analyse one more sample in the same way.

### Observations and Calculations

Weight of 1st sample =  $w_1$  g

Volume of N/10 iodine solution added = 40 ml

Let the volume of N/10  $Na_2S_2O_3$  solution used =  $V_1$  ml

Therefore, volume of N/10 iodine solution used against  $w_1$  g of sample =  $40 - V_1$  ml

or Weight of CaO in the sample =  $(40 - V_1) \times \frac{1}{10} \times \frac{28}{1000}$  g

Therefore, % lime in the 1st sample =  $\frac{(40 - V_1)}{10 \times 1000} \times \frac{28}{w_1} \times 100$

$$= \frac{(40 - V_1)}{w_1} \times 0.28 = A_1$$

Weight of 2nd sample =  $w_2$  g

Let the volume of N/10  $Na_2S_2O_3$  used =  $V_2$  ml



$$\text{Therefore, \% lime in the 2nd sample} = \frac{(40 - V_2)}{w_2} \times 0.28 = A_2$$

$$\text{Therefore, mean \% available lime} = \frac{A_1 + A_2}{2}$$

**Precautions**

CO<sub>2</sub>-free distilled water should be used and excessive contact with atmosphere should be avoided (A sodalime guard tube may be used to prevent absorption of CO<sub>2</sub> from atmosphere).

**Exercise**

203: How do the impurities of CaCO<sub>3</sub> and MgO affect the estimation?

**7.1.2 Determination of Available Lime (after extraction with sucrose solution) with standard acid**

**Reagents Required**

1. Standard hydrochloric acid (N/10)
2. Sucrose solution (10%)
3. Phenolphthalein indicator solution.

**Theory**

A known weight of the sample is slaked by boiling with water (reaction 7.2). Both calcium oxide and hydroxide are then extracted with sucrose solution and filtered. CaCO<sub>3</sub>, MgO and other impurities are left behind. The base in the filtrate is then titrated with standard acid using phenolphthalein indicator.

**Procedure**

Add about 25 ml of boiled-out distilled water to about 0.5 g accurately weighed (by difference method) lime sample taken in an iodine titration flask and boil for 5-10 minutes. Cool, add a few clean dry glass beads and about 100 ml of a 10% sucrose solution. Stopper the flask and shake for 1 minute after every 5 minutes for a period of half an hour. Filter, by suction, through a Buchner funnel. Wash the residue 3-4 times with 10-ml portions of a 5% sucrose solution. Collect the filtrate and washings in a 250-ml measuring flask and make up to the mark with boiled-out distilled water. Take 50 ml of this solution in a titration flask. Add 2 drops of phenolphthalein indicator and titrate with N/10 HCl solution until the pink colour disappears. Take concordant readings.

**Observations and Calculations**

Weight of sample taken =  $w$  g

Volume of lime solution prepared = 250 ml



Volume taken for each titration = 50 ml

Let the concordant volume of N/10  
HCl used

= A ml

$$N_1 V_1 = N_2 V_2$$

(CaO) (HCl)

$$N_1 \times 50 = \frac{1}{10} \times A$$

or  $N_1 = \frac{A}{10 \times 50}$

Therefore, strength of lime solution =  $\frac{A}{10 \times 50} \times 28 \text{ g/l}$

Weight of CaO in w g of the sample =  $\frac{A \times 28}{10 \times 50} \times \frac{250}{1000} \text{ g}$

% Available lime =  $\frac{A \times 28}{10 \times 50} \times \frac{250}{1000} \times \frac{100}{w}$   
 $= \frac{A \times 1.4}{w}$

### Precautions

1. Same as for Experiment 7.1.1 (p. 168).
2. While adding the sugar solution to lime, the flask should be continuously rotated to avoid granulation of lime.

### Exercises

204. What is the function of sucrose in the experiment?
205. What is the purpose of adding glass beads?
206. Why does MgO not interfere in the estimation of lime by this method?
207. (a) What is meant by slaking of lime?  
(b) What are the factors that affect the rate of slaking reaction?
208. How does long exposure of a lime sample to atmosphere affect its available lime?
209. What is meant by the terms Milk of Lime and Lime Water?
210. What is meant by 'Soft' and 'Hard' limes?
211. How are limes classified?

## 7.2 Plant Nutrients

Of the various elements that are known to be essential for the proper growth and reproduction of plants, Nitrogen, Phosphorus and Potassium are required in relatively large amounts and so are known as major elements or




macro-nutrients. A deficiency of one or more of these elements in soil may limit the growth of a particular plant or crop and may thus decrease soil fertility.

### 7.2.1 Nitrogen

It is generally present in soil as ammonium and nitrate ions, and as organic nitrogen compounds. The  $\text{NH}_4^+$  and  $\text{NO}_3^-$  ions are not held firmly by soil and are easily leached away due to excessive irrigation or by rain water. The nitrogen content of soil therefore may get depleted either due to leaching or due to crop raising.

It is estimated that a region with moderate rainfall receives 5 to 7 pounds of nitrogen (a solution of nitrogen oxides formed by lightening) per acre per year. This amount is much less than required and has to be supplemented by

- (a) Planting legume crops occasionally
- (b) Applying organic manures such as animal wastes or compost
- (c) Using commercial fertilizers:
  - (i) Synthetic ammonia or one of its derivatives namely  $\text{NH}_4\text{Cl}$ ,  $(\text{NH}_4)_2\text{SO}_4$ ,  $\text{NH}_4\text{NO}_3$ ,  $\text{NH}_4\text{H}_2\text{PO}_4$  (which provides phosphorus also)
  - (ii) Other inorganic salts— $\text{NaNO}_3$ ,  $\text{Ca}(\text{NO}_3)_2$
  - (iii) Nitrogen in the Organic from such as urea ( $\text{NH}_2\text{CO.NH}_2$ )
  - (iv) Calcium cyanamide which reacts with water slowly and forms urea



For a proper and economical application of manures and fertilizers, a knowledge of their nitrogen content as well as that of the soil is necessary.

### 7.2.2. Determination of the Total Nitrogen Content of Soil, Manure or a Fertilizer

#### Reagents Required

1. Standard sulphuric acid (N/10)
2. Standard sodium hydroxide solution (N/10)
3. Sodium hydroxide solution (50%)
4. Concentrated sulphuric acid
5. Salicylic acid
6. Zinc dust
7. Potassium sulphate
8. Anhydrous copper sulphate
9. Sucrose
10. Ferrous sulphate solution
11. Methyl red indicator solution
12. Red litmus paper.

#### Theory


In the absence of nitrate, nitrogen in the sample is determined by the same





procedure as used for coal (p. 130). Nitrate-nitrogen, however, is lost during digestion with conc.  $\text{H}_2\text{SO}_4$ :




This loss is prevented by treating the nitrate-containing sample with a mixture of salicylic acid and conc.  $\text{H}_2\text{SO}_4$  in cold, when the whole of nitrate is used up in nitrating salicylic acid:



Zinc dust is then added which reacts with sulphuric acid to produce nascent hydrogen which reduces nitrosalicylic acid to amino salicylic acid:



The latter is decomposed during digestion with conc.  $\text{H}_2\text{SO}_4$ , forming ammonium sulphate:



During the digestion stage, nitrogen in other forms (ammoniacal nitrogen and organic nitrogen) is also converted to ammonium sulphate. Distillation with  $\text{NaOH}$  and absorption of liberated ammonia into standard acid followed by back titration of excess of acid completes the total nitrogen determination (p. 131).



*Procedure*(a) *Detection of nitrate*

Shake about 5 g of finely ground representative sample with about 25 ml of hot distilled water and filter. To 1 ml of this solution in a test tube, add 1 ml of freshly prepared ferrous sulphate solution and cool. Add along the sides of the tube a few drops of conc.  $H_2SO_4$ , taking care not to disturb the solution. Formation of a brown or a reddish-coloured ring at the junction of the two liquids indicates the presence of nitrate.

(b) *Determination of Nitrogen*

When nitrate is absent, proceed as for the determination of nitrogen in coal (p. 130). In the presence of nitrate, proceed as under:

Transfer a known weight (0.5-5 g, depending upon the nitrogen content) of the sample into a Kjeldahl's flask. Mix 2 g of salicylic acid with about 40 ml of conc.  $H_2SO_4$  in a beaker and add the acid mixture to the Kjeldahl's flask, in one lot so that it covers the whole of the sample at once. Immerse the flask in cold water and allow the reaction to proceed for about half an hour, occasionally shaking the reaction mixture. Take out the Kjeldahl's flask from the cold bath and add 1-2 g zinc dust in small portions with constant shaking. When the reaction subsides, heat gently until the frothing ceases. Add about 10 g of  $K_2SO_4$  and either 0.2 g of Se powder or 0.5 g of anhydrous  $CuSO_4$  or 0.3 g of cupric selenite dihydrate ( $CuSeO_3 \cdot 2H_2O$ ), followed by about 10-15 ml concentrated  $H_2SO_4$  and proceed as described on page 131.

*Precautions*

1. An appreciable rise of temperature during the digestion of the sample with sulphuric acid-salicylic acid mixture should be avoided as it may lead to loss of nitrogen.
2. See precautions 1 to 6 (page 131).

*Observations and Calculations*

Same as for nitrogen in coal (see page 131-2).

*Exercises*

212. How does the slow addition of acid-mixture to the nitrate sample affect the determination?
213. Name some other organic compounds that form nitroderivatives under the conditions of the experiment.
214. Name some other reagent that is employed in place of zinc for the reduction of nitrosalicylic acid.
215. What is meant by 'Crop Rotation'? What is its advantage?
216. What is 'Organic Farming'? What are its advantages?
217. What is compost? How is it obtained?
218. What is the effect of application of excess fertilizer?



### 7.2.3 Phosphorus

On an average, a ton of good soil holds about a pound of phosphorus. The whole of this phosphorus may not be in a form that can be taken up by the plants, yet the determination of the total phosphorus content of the soil is important because a decrease in it will point to a fall in the availability of phosphorus to plants. Luckily, the orthophosphate ion, which is an available form of phosphorus, is held tenaciously by the soil and is not easily removed by leaching as is the case with nitrate, chloride and sulphate. However, with the introduction of intensive agriculture, more and more phosphorus is taken up by the plants into their foliage and fruits and, as it is not replenished by nature, its deficiency has to be overcome by the application of a fertilizer containing calcium phosphate and/or ammonium phosphate. The usefulness and the value of a fertilizer will depend on its phosphorus content and hence the need for its determination.

Phosphate rock is the principal raw material for the manufacture of superphosphate, a water soluble mixture of  $\text{Ca}(\text{H}_2\text{PO}_4)_2$  and  $\text{CaSO}_4$ , which is obtained by treating finely ground rock phosphate with roughly an equal amount of sulphuric acid. Determination of  $\text{Ca}_3(\text{PO}_4)_2$  content of the phosphate rock is essential for fixing the price of the rock and for exploring the economic feasibility of the manufacture of superphosphate from the rock.

#### *Preparation of Solution*

(a) *For Soil and Fertilisers*—Take about 2 g of accurately weighed and finely ground representative sample in a Kjeldahl's flask and add about 25 ml of conc.  $\text{HNO}_3$ . Boil gently for about half an hour to remove all the easily oxidisable organic matter. Cool and add about 15 ml of 70% perchloric acid. Boil again until the solution becomes almost colourless and dense white fumes appear. Continue boiling for another 5 minutes and cool slightly. Add about 50 ml of distilled water & boil for a few minutes. Cool and filter into a 250-ml measuring flask. Wash the residue with hot water and make up the volume upto the mark.

When organic matter content is small, the following method with aqua regia may be adopted:

(b) *For Phosphate Rock*—Take about 2 g of accurately weighed and finely pulverised (to pass a 60-mesh sieve) representative sample of phosphate rock in a 250-ml conical flask. Add about 25 ml dilute aqua regia (1 part conc.  $\text{HCl}$  + 1 part conc.  $\text{HNO}_3$  + 2 parts distilled water) and boil gently until the evolution of brown fumes stops. Cool and filter into a 250-ml measuring flask. Wash the residue with hot distilled water and make the volume upto the mark.

### 7.2.4 Determination of Phosphate Content of the given soil extract, fertilizer solution or phosphate rock solution

#### *Reagents required*


1. Standard hydrochloric acid (N/10)




2. Standard sodium hydroxide solution (N/10)
3. Ammonium molybdate solution (5%)
4. Conc.  $\text{HNO}_3$
5. Ammonium nitrate
6. Potassium nitrate solution (1% or 0.1 M)
7. Phenolphthalein indicator solution
8. Methyl red indicator solution.

### Theory

When an excess of ammonium molybdate solution is added to the phosphate solution in the presence of nitric acid, a yellow precipitate of varying composition from  $(\text{NH}_4)_3\text{PO}_4 \cdot 12\text{MoO}_3$  to  $(\text{NH}_4)_3\text{PO}_4 \cdot 12\text{MoO}_3 \cdot 2\text{H}_2\text{O}$  is obtained. Upon suitably washing the precipitate with dilute  $\text{KNO}_3$  solution the acid is completely removed and the precipitate is converted to ammonium phospho-molybdate with the composition  $(\text{NH}_4)_3\text{PO}_4 \cdot 12\text{MoO}_3$ .



The washed precipitate is then treated with a known excess of standard  $\text{NaOH}$  which dissolves the precipitate as per the following reaction:



The excess of  $\text{NaOH}$  is titrated with standard acid using phenolphthalein indicator. The amount of phosphate in the given solution is calculated from the volume of the standard alkali consumed, using the reaction (7.14) which indicates that 1 gram-atom of phosphorus is equivalent to 23 gram-moles of  $\text{NaOH}$ .

### Procedure

Pipet out 20 ml or a suitable aliquot (corresponding to 12-50 mg  $\text{P}_2\text{O}_5$ ) of the given solution into a 250-ml glass-stoppered flask. Add about 8 g of  $\text{NH}_4\text{NO}_3$  and 5 ml of concentrated  $\text{HNO}_3$ . Shake to dissolve and dilute to about 100 ml with distilled water. Take about 50 ml of a freshly prepared 5% ammonium molybdate solution into another flask. Heat both the solutions on a water bath to a temperature of  $40-45^\circ\text{C}$  and, while shaking continuously, add the ammonium molybdate solution slowly to the phosphate mixture. A yellow precipitate appears. Now fit the flask with the glass stopper, shake vigorously for about 10 minutes and allow to stand for half an hour on the water bath ( $40-45^\circ\text{C}$ ). Filter by decantation through a Whatman filter paper No. 5. Now transfer, as far as possible, the precipitate to the filter paper and wash the flask and the precipitate repeatedly with small amounts of 1%  $\text{KNO}_3$  solution until the filtrate is no longer acidic. Now return the precipitate, together with the filter paper, to the flask in which precipitation was carried out. Add with a pipet, 40 ml of N/10  $\text{NaOH}$  solution. Stopper the flask and shake to dissolve the yellow precipitate (If the whole of the precipitate is not dissolved, a further measured amount, say 10 ml, of N/10  $\text{NaOH}$  should be



added). Dilute to about 100 ml, add 2-3 drops of phenolphthalein indicator and titrate with N/10 HCl until the pink colour is completely discharged.

#### Precautions

- (1) Perchloric acid should not be added to samples containing easily oxidisable organic matter, otherwise an explosive reaction might take place.
- (2) If there is a turbidity in the ammonium molybdate solution, it should be filtered before use.
- (3) The temperature of the solution should not be allowed to go beyond  $45^{\circ}\text{C}$ .
- (4) The washing liquid should each time be taken first in the flask in which the precipitation was carried out, well shaken so that the whole of the inner surface of the flask and any precipitate sticking to it is thoroughly washed and then it should be poured over the precipitate on the filter paper.
- (5) A second fraction of the washing liquid should be used only when the first fraction has completely passed through the filter paper. If the two fractions are allowed to mix, the washing will remain incomplete.
- (6) The standard sodium hydroxide solution must be free from sodium carbonate.
- (7) The alkali solution should be added to the flask through the funnel in which filtration took place so as to dissolve any precipitate remaining on its sides.
- (8) The funnel then should be rinsed into the flask with distilled water.

#### Observations and Calculations

Weight of the sample taken  $\quad\quad\quad = W \text{ g}$

Volume of the extract prepared  $\quad\quad\quad = 250 \text{ ml}$

Volume of extract taken for determination  $\quad\quad\quad = 20 \text{ ml}$

Volume of N/10 NaOH added  $\quad\quad\quad = 40 \text{ ml}$

Volume of N/10 HCl used for titrating excess of alkali  $\quad\quad\quad = A \text{ ml}$

Hence volume of N/10 NaOH left unused  $\quad\quad\quad = A \text{ ml}$

Or volume of N/10 NaOH consumed by ammonium phosphomolybdate obtained from 20 ml of extract  $\quad\quad\quad = (40 - A) \text{ ml}$

From reaction (7.14)

23 g-mole of NaOH  $\quad\quad\quad \equiv 1 \text{ g mole of } (\text{NH}_4)_3\text{PO}_4 \cdot 12\text{MoO}_3$

or 23 litres of 1 N NaOH  $\quad\quad\quad \equiv 31 \text{ g P} \equiv 71 \text{ g P}_2\text{O}_5$

Or 1 litre of N/10 NaOH  $\quad\quad\quad \equiv \frac{71}{23 \times 10} \text{ g P}_2\text{O}_5$



$$\text{or } (40-A) \text{ ml N/10 NaOH} \quad \equiv \frac{71}{23 \times 10} \times \frac{(40-A)}{1000} \text{ g P}_2\text{O}_5$$

$$\text{Hence phosphate content of 20 ml of extract} \quad = \frac{71}{23 \times 10} \times \frac{(40-A)}{1000} \text{ g P}_2\text{O}_5$$

$$\text{or strength of extract} \quad = \frac{71}{23 \times 10} \times \frac{(40-A)}{1000} \times \frac{1000}{20} \text{ g P}_2\text{O}_5/\text{litre}$$

$$\begin{aligned} \text{or \% of P}_2\text{O}_5 \text{ in soil or fertilizer} &= \frac{71}{23 \times 10} \times \frac{(40-A)}{1000} \times \frac{1000}{20} \times \frac{250}{1000} \times \frac{100}{w} \\ &= \frac{71}{23 \times 10} \times \frac{(40-A)}{w} \times 1.25 \end{aligned}$$

Results of phosphate rock are generally reported in terms of % of  $\text{Ca}_3(\text{PO}_4)_2$ .

$$\begin{array}{ccc} \text{P}_2\text{O}_5 & \equiv & \text{Ca}_3(\text{PO}_4)_2 \\ (142) & & (310) \\ 71 & & 155 \end{array}$$

$$\text{Strength of extract} \quad = \frac{155}{23 \times 10} \times \frac{(40-A)}{1000} \times \frac{1000}{20} \text{ g/l of Ca}_3(\text{PO}_4)_2$$

$$\% \text{ of Ca}_3(\text{PO}_4)_2 \text{ in the phosphate rock} \quad = \frac{155}{23 \times 10} \times \frac{(40-A)}{w} \times 1.25$$

### Exercises

219. Why is it necessary not to heat the solutions above  $45^\circ\text{C}$ ?
220. The filtrate from the ammonium phosphomolybdate precipitate is yellow coloured. What does it indicate?
221. What test should be performed to be sure that the filtrate contains no acid?
222. What is a fertilizer?
223. List the elements known to be essential for plant growth.
224. What is meant by N-P-K value of a fertilizer?
225. What is the general composition of a phosphate rock?
226. What does B.P.L. stand for?
227. What is meant by available or assimilable phosphorus?
228. How is citrate-insoluble phosphorus determined?
229. List the forms in which nitrogen, phosphorus and potassium are generally absorbed by plants.


### 7.3 Bleaching Powder

Bleaching powder, also called 'Chloride of Lime' or Bleach, in trade, is the most commonly used material for bleaching cellulose, cotton yarn & textile and linen. It is a very important and cheap commercial product, used widely



as a disinfectant for potable water, for making wool unshrinkable, in petroleum refining, in the manufacture of chloroform, in the laboratory as a source of oxygen & chlorine, and as an oxidising agent.

It is prepared by passing chlorine gas over slaked lime at a temperature of 35-45°C (considerable amounts of chlorate being formed at higher temperature). Majority of its reactions can be conveniently explained by assuming it to be a mixed calcium hypochlorite-chloride  $[\text{Ca}(\text{OCl})\text{Cl}]$ . However, X-ray examination has shown bleaching powder to be a mixture of calcium hypochlorite  $[\text{Ca}(\text{OCl})_2 \cdot 4\text{H}_2\text{O}]$  and basic calcium chloride  $[\text{CaCl}_2 \cdot \text{Ca}(\text{OH})_2 \cdot \text{H}_2\text{O}]$ , some free slaked lime being also present. Hypochlorite is the actual constituent which is responsible for liberation of  $\text{Cl}_2$  when bleaching powder is acidified:



The bleaching, oxidizing or disinfecting value of a sample depends on the percentage of chlorine thus liberated, i.e., grams of chlorine liberated from 100 grams of the sample when treated with dilute acid. This is referred to as 'Available Chlorine' or 'Bleaching Chlorine' and forms the basis on which bleaching powder is marketed.

Continuous decomposition of bleaching powder during storage is its chief drawback. Being hygroscopic, it absorbs moisture from atmosphere and evolves chlorine:



Due to this deterioration on standing, a sample of bleaching powder may always contain less amount of chlorine than what is expected and therefore, before use, every sample must be analysed for its effective or available chlorine.



### 7.3.1 Determination of the percentage of 'Available Chlorine' in a given sample of Bleaching Powder by Bunsen's Method

#### Reagents Required

1. Standard sodium thiosulphate solution (N/10)
2. Potassium iodide solution (10%)
3. Dilute  $\text{H}_2\text{SO}_4$
4. Freshly prepared starch solution.


#### Theory

The bleaching powder solution or suspension is treated with an excess of KI solution and then acidified with dilute  $\text{H}_2\text{SO}_4$ :





The liberated iodine is titrated with a standard solution of sodium thio-sulphate, using starch solution as indicator near the end-point:



### Procedure

Remove and discard outside layer of the sample (which may have lost some chlorine). Mix the sample well, quickly transfer to a stoppered bottle and weigh. Transfer about 4 g of it to a porcelain mortar and weigh the bottle again. Put some distilled water on to the sample in the mortar and with a pestle rub the mixture to a smooth cream. Add more water, grind with the pestle, let settle for a while and decant the milky solution into a 500-ml measuring flask. Grind the residue with more water and pour off the liquid into the measuring flask as before. Repeat the operation until the sample is quantitatively transferred to the flask. Add distilled water to make up the volume upto the mark and mix well.

Transfer 50 ml of the above solution or suspension (with a mechanical pipet, burette or a measuring cylinder) to a 250-ml conical flask containing about 25 ml of a 10% solution of KI. Add 10 ml of dilute  $\text{H}_2\text{SO}_4$  and run in, from the burette, standard N/10  $\text{Na}_2\text{S}_2\text{O}_3$  solution until the colour of the solution becomes very light yellow. Add 2 ml of freshly prepared starch solution, mix and complete the titration to the disappearance of blue colour. Repeat to get concordant readings.

### Precautions

- (1) During weighing, the sample bottle should be kept stoppered otherwise chlorine evolved due to the decomposition of the sample may corrode the material of the balance.
- (2) The solution, being unstable, should be titrated immediately after its preparation.
- (3) The solution should be well shaken before each aliquot is withdrawn for titration.
- (4) Chlorine vapours being harmful, the solution should not be sucked into the pipet with mouth.
- (5) The bleaching powder solution should not be acidified in the absence of KI otherwise some chlorine will be lost.
- (6) If iron is present in the sample, phosphoric acid should be used in place of  $\text{H}_2\text{SO}_4$  to prevent the reaction of iron with iodide.

### Observations and calculations

Initial weight of the sample bottle	= $w_1$ g
Final weight of the sample bottle	= $w_2$ g



Weight of sample taken	$= (w_1 - w_2) \text{ g}$
Volume of solution prepared	$= 500 \text{ ml}$
Volume of solution taken for each titration	$= 50 \text{ ml}$
Concordant volume of N/10 $\text{Na}_2\text{S}_2\text{O}_3$ used	$= A \text{ ml}$
$N_1 V_1$	$= N_2 V_2$
(Bleaching Powder)	( $\text{Na}_2\text{S}_2\text{O}_3$ )

$$N_1 \times 50 = \frac{1}{10} \times A$$

$$\text{or } N_1 = \frac{A}{10 \times 50}$$

$$\text{Therefore amount of chlorine per litre of the solution} = \frac{A \times 35.5}{10 \times 50} \text{ g}$$

$$\begin{aligned} \text{or \% Available Chlorine} &= \frac{A \times 35.5}{10 \times 50} \times \frac{500}{1000} \times \frac{100}{(w_1 - w_2)} \\ &= \frac{A \times 3.55}{(w_1 - w_2)} \end{aligned}$$

### Exercises

230. Write the ionic reaction representing the formation of bleaching powder.
231. Explain why starch-iodine blue colour reappears after the end-point if acetic acid is used instead of sulphuric acid for acidification.
232. In this estimation, can  $\text{H}_2\text{SO}_4$  be replaced with  $\text{HCl}$ ?
233. Outline the method that is considered to be more accurate than the iodometric method.
234. What is meant by bleach liquor? How is it prepared?
235. Describe the process of bleaching cloth.
236. List the important specifications for a good bleaching powder.
237. What is the French Scale for reporting the strength of a bleaching powder sample?
238. List some other reagents that are commonly used as bleaching agents.

### 7.4 Surface Tension

The molecules present in the surface of a liquid experience a resultant downward pull because the number of molecules below the surface, i.e., in the bulk of the liquid is much larger than the number of molecules above it, i.e., in the vapour phase. Consequently, the molecules in the surface tend to



be drawn inside, with the result that the liquid surface tends to contract and behaves as if it were in a state of tension. This tension or force which acts along the surface of the liquid, uniformly in all directions, is known as *Surface Tension*. Numerically, it is equal to the force in dynes/cm acting along the surface at right angles to any imaginary line in the surface and is designated by  $\gamma$  (gamma).

As a consequence of surface tension, the drops of a liquid or bubbles of a gas are spherical in shape—rain drops and mercury drops are common examples. Smaller drops coalesce to give bigger drops because the process involves decrease in surface area (The phenomenon is utilized in collecting split Hg droplets).

The rise of a liquid into a capillary tube, which is wetted by the liquid, is directly proportional to the surface tension of the liquid. Common examples of the phenomenon are rise of oil in the wick of a lamp, rise of underground water on to the surface of earth, rise of ground water through the capillaries of plants to the twigs and leaves. Surface tension of a lubricant is important in capillary or wick lubrication methods.

High surface tension leads to superheating and bumping or spurring during boiling (Sugar and starch increase the surface tension of water and are mainly responsible for bumping in cooking pots). Decrease in surface tension of water, due to certain salts or oils in the boiler, helps in the rapid formation of steam bubbles but may lead to priming and foaming (wet steaming) which is prevented by spreading on the surface of water a layer of castor oil which increases the surface tension.

Surface tension of the liquid is utilized in transferring the liquid from the condenser to the evaporator in the heat-pipe exchanger for waste heat recovery.

Surface tension measurements were used for investigating molecular structures through parachor values. The method is no longer in use.

### *Measurement of Surface Tension*

The capillary rise method for measurement of surface tension, though it is used to get most accurate result in absolute terms, is not in common use as it is extremely laborious, time consuming and requires a large amount of the liquid.

Of the methods based on comparison with liquids of accurately known surface tension, the torsion balance or tensiometer method is the quickest and requires only a very small amount of the liquid; but if water is to be used as the standard liquid, the room must be free from organic vapours which interfere by impairing the water-air interface. This method is commonly used for industrial measurement.

The Drop Number Method, because of its practical convenience and a good degree of reliability, is commonly employed for laboratory measurement of surface tension.



### 7.4.1 Determination of Surface Tension of a liquid, say $\text{CCl}_4$ , benzene, alcohol, etc., by Drop Number Method

#### Theory

The method is based on the principle that when a liquid is allowed to pass through a capillary tube, held vertically, at such a slow speed that the drops fall off the tip of the capillary under their own weight and are not pushed away by the kinetic force of flow or vibrations, the weight of a drop is approximately proportional to the surface tension of the liquid. Thus, if two liquids with surface tensions  $\gamma_1$  and  $\gamma_2$  are passed through the same capillary tube, then

$$\frac{\gamma_1}{\gamma_2} = \frac{w_1}{w_2} \quad (7.20)$$

where  $w_1$  and  $w_2$  are mean weights of their drops falling off the capillary end.

It is often more convenient to count the number of drops formed from a given volume of a liquid than finding the weights of single drops. Let  $n_1$  and  $n_2$  be the number of drops produced when equal volumes ( $V$  ml) of the two liquids are allowed to fall through the same capillary. Then,

$$\text{the mean volume of a drop of one liquid} = \frac{V}{n_1}$$

$$\text{and the mean volume of a drop of the second liquid} = \frac{V}{n_2}$$

If  $d_1$  and  $d_2$  respectively be the densities of liquids 1 and 2, then the mean weights  $w_1$  and  $w_2$  of their drops are given by

$$w_1 = \frac{V}{n_1} d_1 \quad \text{and} \quad w_2 = \frac{V}{n_2} d_2$$

Then from equation (7.20)

$$\frac{\gamma_1}{\gamma_2} = \frac{w_1}{w_2} = \frac{V}{n_1} d_1 \times \frac{n_2}{V d_2} = \frac{n_2 d_1}{n_1 d_2} \quad (7.21)$$

One of the liquids is usually water whose surface tension and density, at different temperatures, are accurately known. The density of the liquid under test may be determined by specific gravity bottle.

The capillary tube, through which the drops of the liquid fall, forms the lower part of a pipet - as shown in Figure 13-and is then called a Drop Pipet or Stalagmometer.

#### Requirements

1. A wide-mouth receiving bottle with a tightly fitting rubber stopper having two holes through which pass a stalagmometer and a glass tube
2. A small rubber tubing with a screw-pinch-cock
3. A clamp stand






Fig. 13 Measurement of Surface Tension.

- |                                  |                             |
|----------------------------------|-----------------------------|
| A—Wide mouth receiving bottle    | F—Screw-pinchock            |
| B—Tightly fitting rubber stopper | G—Thermostat                |
| C—Stalagmometer                  | H—Liquid under test         |
| D—Glass tube                     | I—Clamp                     |
| E—Rubber tubing                  | T <sub>1</sub> —Thermometer |

4. A thermometer
5. A thermostat (or a beaker full of water)
6. Distilled water, and
7. The liquid whose surface tension is to be measured.

### Procedure

Thoroughly clean the stalagmometer and the receiving bottle, first with alkali and then with chromic acid mixture. Finally, rinse several times with distilled water. To the top of the stalagmometer, attach the rubber tubing with the screw-pinchock. Immerse the lower end of the stalagmometer into distilled water and suck through the rubber tubing until the level of water rises above the mark X. Close the screw-pinchock and fit the rubber stopper carrying the stalagmometer and a glass tube into the mouth of the receiving bottle. Place the whole assembly in the thermostatic bath and hold the stalagmometer vertical with the help of a clamp. Allow the stalagmometer to attain the temperature of the bath. Slightly open the screw-pinchock and count the number of drops as the liquid meniscus falls from the mark X to the mark Y. Repeat the process to record a number of observations.

Take out the whole assembly from the bath and dismantle the stalagmometer from the receiving bottle. Rinse the stalagmometer, the glass tube and the bottle with alcohol and dry. Now fill the stalagmometer with the liquid



under test, mount it onto the receiving bottle and replace in the bath. Determine the number of drops for the fixed volume of the liquid between the two marks X and Y, as with water. Repeat to take a number of readings. Record the temperature of the bath.

#### *For determination of density*

Properly clean the specific gravity bottle, rinse it with water, dry and weigh. Now fill it with distilled water and weigh. Empty the bottle, rinse with alcohol and dry. Fill it with the liquid under test and weigh.

#### *Precautions*

- (1) After washing the stalagmometer perfectly free from any trace of grease, it should be ensured that its tip does not come in contact with hands or the working table.
- (2) While closing the screw-pinch-cock, care should be taken that the liquid meniscus does not fall below the mark X.
- (3) The number of drops per minute should not exceed 10, otherwise they may not be properly formed.
- (4) While counting the drops, all vibrations or disturbances of the stalagmometer should be avoided.
- (5) To avoid evaporation from the surface of drops, a small amount of the liquid should be taken in the receiving bottle and the drop formation should be close to the surface of the liquid.
- (6) As far as possible, the temperature of the bath should remain constant.
- (7) Only those observations should be taken into account for which the drop numbers do not vary by more than 0.5.

#### *Observations and Calculations*

Temperature of bath  $= t^{\circ}\text{C}$

Surface tension of water at  $t^{\circ}\text{C}$   $= \gamma_2$

Weight of empty specific gravity bottle  $= w_1 \text{ g}$

Weight of specific gravity bottle + water  $= w_2 \text{ g}$

Weight of specific gravity bottle + liquid  $= w_3 \text{ g}$

Therefore, 
$$\frac{\text{Density of liquid}}{\text{Density of water}} = \frac{d_1}{d_2} = \frac{w_3 - w_1}{w_2 - w_1}$$

Surface tension of the liquid  $\gamma_1 = \gamma_2 \cdot \frac{d_1}{d_2} \cdot \frac{n_2}{n_1} \quad (7.21)$

$$= \gamma_2 \cdot \frac{w_3 - w_1}{w_2 - w_1} \cdot \frac{n_2}{n_1}$$



Liquid	No. of drops from fixed volume	Mean
Water	1 _____	$n_2$
	2 _____	
	3 _____	
	4 _____	
Test Liquid	1 _____	$n_1$
	2 _____	
	3 _____	
	4 _____	

**Exercises**

239. Why is the lower end or tip of the stalagmometer flattened?
240. What is the function of the narrow capillary in the stalagmometer?
241. Why is the stalagmometer tube graduated above and below the bulb?
242. What is the glass tube meant for?
243. What is the effect of temperature on the surface tension of a liquid?
244. What is Interfacial Tension?
245. Why is the value of interfacial tension between two immiscible liquids less than the value for the liquid with higher surface tension?
246. What is parachor?
247. What are surface active agents?
248. What is surface energy?



## Answers to Exercises

1. A primary standard is a substance that is available in pure state, or whose purity with respect to the active component is known, and remains stable during storage, drying and weighing so that its standard solution (a solution of definite normality) can be prepared by diluting its accurately weighed amount to a definite volume.

### Examples

- (i) For acid-base reactions:

- (a)  $\text{Na}_2\text{CO}_3$  (Mol. wt. 106, Eq. wt. 106 for half neutralisation and 53 for complete neutralisation),
- (b) Sodium tetraborate,  $\text{Na}_2\text{B}_4\text{O}_7 \cdot 10\text{H}_2\text{O}$   
(Mol. wt. 381.42, Eq. wt. 190.71)
- (c) Potassium hydrogen phthalate,  $\text{KH} \cdot \text{C}_8\text{H}_4\text{O}_4$   
(Mol. wt. and Eq. wt. 204.22).

- (ii) For precipitation reactions:

- (a)  $\text{AgNO}_3$  (Mol. wt. and Eq. wt. 169.89)
- (b)  $\text{KCl}$  (Mol. wt. and Eq. wt. 74.557)
- (c)  $\text{KSCN}$  (Mol. wt. and Eq. wt. 97.185).

- (iii) For redox reactions:

- (a)  $\text{K}_2\text{Cr}_2\text{O}_7$  (Mol. wt. 294.22, Eq. wt. 49.035)
- (b) Sodium oxalate,  $\text{Na}_2\text{C}_2\text{O}_4$   
(Mol. wt. 134.01, Eq. wt. 67).

- (iv) For complexometric titrations:

- (a) Disodium salt of EDTA (Mol. wt. 372.25, Eq. wt. 186.125)
- (b)  $\text{CaCO}_3$  (Mol. wt. 100, Eq. wt. 50)

2. A solution of slightly higher concentration than desired (say N/8 or N/9) is first prepared. It is then standardised by titrating against a standard solution of a suitable primary standard. The solution of definite normality is then prepared by appropriate dilution.

3. Strength of sodium oxalate solution = 3.35 g/l  
Eq. wt. of sodium oxalate = 67



$$\begin{aligned}\text{Normality of sodium oxalate solution, } N_1 &= \frac{3.35}{67} \\ &= \frac{1}{20}\end{aligned}$$

$$\text{Volume of sodium oxalate solution taken } V_1 = 20 \text{ ml}$$

$$\text{Volume of unknown } \text{KMnO}_4 \text{ solution used, } V_2 = 19 \text{ ml}$$

$$N_1 V_1 = N_2 V_2$$

$$\begin{array}{cc} \text{(Sod. oxalate)} & \text{(KMnO}_4\text{)} \end{array}$$

$$\frac{1}{20} \times 20 = N_2 \times 19$$

$$\text{Therefore, } N_2, \text{ the normality of the given solution} = \frac{1}{19}$$

$$\text{Normality of desired solution, } N_3 = \frac{1}{20}$$

$$\text{Volume of the solution desired, } V_3 = 500 \text{ ml}$$

$$\begin{aligned}\text{Let the volume of the given} \\ \text{KMnO}_4 \text{ solution to be diluted} &= V_2 \text{ ml}\end{aligned}$$

$$\begin{aligned}\text{Then } N_2 V_2 &= N_3 V_3\end{aligned}$$

$$\frac{1}{19} \times V_2 = \frac{1}{20} \times 500$$

$$\text{or } V_2 = \frac{1}{20} \times 500 \times 19 = 475 \text{ ml}$$

Thus, 475 ml of the given solution should be diluted to 500 ml to get  $N/20 \text{ KMnO}_4$ .

4. Solutions prepared in boiled-out distilled water are more stable, i.e., they can be stored for much longer durations without any appreciable change in strength because boiling of water
  - (i) Removes dissolved oxygen which when present may slowly react with many reducing agents.
  - (ii) Removes dissolved carbon dioxide which interferes in acid-alkali reactions and may slowly decompose many reagents.
  - (iii) Destroys bacteria that may slowly deteriorate many solutions due to biochemical activity.
5. 20 g of NaOH pellets are dissolved in 20 ml of boiled-out distilled water by stirring with a glass rod. The solution is transferred to a pyrex glass tube, closed with a stopper covered with tin foil and allowed to stand undisturbed. Sodium carbonate, being insoluble in a concentrated solution of sodium hydroxide, settles down. To prepare approximately



N/10 NaOH, about 8 ml of the supernatant liquid is taken out with a graduated pipet and diluted to 1 litre with boiled-out distilled water. [Exact normality is determined by standardisation with potassium hydrogen phthalate].

6. Because the permanganate solution is decomposed by the organic matter present in both the filter paper and the rubber tubing.
7. (a) The concentration equilibrium constant

$$K_c = \frac{[L]^l \times [M]^m \times \dots}{[A]^a \times [B]^b \times \dots}$$

and the partial pressures equilibrium constant

$$K_p = \frac{[pL]^l \times [pM]^m \times \dots}{[pA]^a \times [pB]^b \times \dots}$$

$$(b) K_p = K_c \times (RT)^{\Delta n}$$

where,  $\Delta n$  = No. of moles of gaseous products — No. of moles of gaseous reactants

R = Gas constant

T = Absolute temperature

8. (a) The rates of forward and backward reactions are equal.  
(b) The free energy of the reactants is equal to the free energy of the products, i.e., the free energy change of the process is zero.
9. Equilibrium is characterized by constancy of some properties but it is not the only requirement. When some of the properties of a system are constant but equilibrium does not exist, the system is said to be in a steady state. In the experimental determination of calorific value of a gaseous fuel by Boy's Gas Calorimeter, the following conditions characterise the steady state:
  - (a) Air/fuel mixture under constant pressure burns at a constant rate.
  - (b) The rate of flow of water through the copper tubing becomes constant.
  - (c) The inlet and outlet temperature becomes constant. Though the temperature is not uniform throughout, it does not change with time.

However, it is an open system; the fuel and air are continuously entering, chemical change (combustion) is taking place and the products of combustion ( $\text{CO}_2$ ,  $\text{H}_2\text{O}$  &  $\text{N}_2$ ) are continuously leaving the system. Equilibrium can exist only in a closed system (a constant amount of matter) at a uniform temperature.



Another example of steady state is boiling of water in an open pan at constant temperature. The vapour pressure of water remains constant (equal to the atmospheric pressure) but the amount of water in the pan is continuously decreasing.

10. (a) A positive value of  $\Delta H$  indicates that the dissociation of  $N_2O_4$  (a colourless gas) to give  $NO_2$  (a gas with a reddish-brown colour) is an endothermic reaction, i.e., it proceeds with absorption of heat. Heating the above system will tend to raise its temperature. In accord with Le Chatelier's principle, the equilibrium should shift in the forward direction so that a portion of heat that caused the temperature rise is absorbed. The forward shift will lead to formation of more  $NO_2$  and therefore an increase in the intensity of the reddish-brown colour is expected. Similarly, on cooling a reversal of the above process is expected, i.e., the intensity of the reddish-brown colour should decrease.
- (b) That the predictions are correct can be shown by taking two identical glass bulbs (100-ml round-bottom flasks may be used), filling them to equal pressure of  $NO_2$  and closing with tightly fitting stoppers. On immersing one of the bulbs (A) in ice-water and the other (B) in boiling water, it is seen that intensity of colour in bulb A starts fading while in B it starts intensifying. If the two bulbs are now taken out and immersed in the same water bath at room temperature, it is seen that the intensity of colour in A increases and that in B decreases until the two bulbs have identical colours.

It must, however, be ensured that initial pressures (and therefore the concentrations) of  $NO_2$  in the two bulbs are exactly equal, and sufficient time should be allowed for the equilibrium to be reached.

11. They help in predicting the effect of changing the concentration of one or more of the reactants or the products, temperature and pressure on the state of equilibrium of a given system. With this knowledge, optimum conditions for getting maximum yield of a product can be chosen and thus the process can be made most economical.

The equilibrium



represents the well-known industrial process (Haber process) for the manufacture of ammonia.

- (a) *Effect of pressure:* Increase in pressure over a system decreases the volume. The total number of moles per unit volume therefore increases. This change can be counteracted in part if some  $N_2$  combines with  $H_2$  to form  $NH_3$  (as production of ammonia represents a decrease in moles from 4 to 2). Therefore, in





accordance with Le Chatelier's principle, increase in pressure will increase the yield of ammonia (Increase in pressure shifts the equilibrium in a direction in which the total number of moles of gaseous substances decreases). As it is expensive to build high pressure equipment, a compromise pressure of 350 atmospheres is chosen.

- (b) *Effect of temperature:* Increase in temperature of a system at equilibrium makes the reaction proceed in a direction in which heat is absorbed [Ex. 10(a)]. In accord with Le Chatelier's principle, therefore, rise in temperature will favour dissociation of ammonia and will thus lead to decrease in yield. At low temperature, however, the rate of reaction decreases. So, a compromise temperature of  $500^{\circ}\text{C}$  is chosen and a catalyst (Fe) is used to further raise the rate of reaction.



12. (i) *Formation of insoluble substances:* Use is made of the knowledge of solubility product principle, solubility product constant and the common ion effect.

#### Examples


- (a) Removal of metal ions from industrial wastes:



- (b) Water softening by lime soda process:




- (c) Phosphate conditioning of boiler-feed water:



- (ii) *Addition of a reagent that will combine with one of the ions to form a weakly ionized compound*


#### Examples

- (a) Neutralisation of acid and alkali:










- (b) Dissolution of precipitate of metal hydroxides:

(iii) *Formation of complexes*


- (a) Dissolution of precipitates:




- (b) Removal of cyanide from industrial wastes:





- (iv)
- Formation of a gaseous product*
- : The gas formed leaves the sphere of reaction and the reaction is forced to completion, e.g., dissolution of metallic sulphides such as FeS in HCl



- (v)
- Oxidation and reduction*
- : One or more of the ions involved are destroyed, e.g., oxidation of cyanide in industrial wastes by chlorination in alkaline medium:



13. Ammonium hydroxide does precipitate both
- $\text{Cu}^{2+}$
- and
- $\text{Zn}^{2+}$
- as the corresponding hydroxides:




but excess  $\text{NH}_4\text{OH}$  reacts with the precipitates dissolving them by forming complexes [Ex. 12(iii)a].

14. Reactions in which the products do not combine to reproduce the reactants are termed as irreversible reactions.

**Examples**


- (i) The decomposition of
- $\text{KClO}_3$
- into potassium chloride and oxygen even in a closed vessel:



$\text{KCl}$  and  $\text{O}_2$  do not react to form  $\text{KClO}_3$ .



(ii) The decomposition of ammonium nitrite:




$\text{N}_2$  and  $\text{H}_2\text{O}(\text{g})$  do not react to form  $\text{NH}_4\text{NO}_2$ .

15. The volume of  $\text{HIO}_3$  added to flask B is 10 ml more than that added to flasks A and C. Therefore, addition of 10 ml less distilled water to flask B gives same volume of the total solution and hence the same bisulphite ion concentration in all the three flasks.
16. Addition of more water will decrease the concentration of both the reactants ( $\text{HIO}_3$  and  $\text{NaHSO}_3$ ). This is expected to reduce the rate of reaction and appearance of blue colour should be delayed.
17. Many reactions are known to occur in two or more elementary steps. In such cases, the product(s) of one step become(s) the reactant(s) for the next step. Such reactions are known as consecutive reactions or complex reactions.

The rates of the various steps generally differ from one another. It is apparent that the rate of the overall reaction cannot be faster than the step which takes place at slowest rate. The slowest step, in the sequence of various steps, is called the 'rate-determining' step because its rate will be approximately equal to the rate of the overall reaction. This approximation is called the Principle of bottle-neck.

In the reaction between  $\text{HIO}_3$  and  $\text{NaHSO}_3$ , the rate-determining step is 2.17:




18. A clock reaction consists of a series of consecutively occurring reactions. The reaction goes on for a period of time without giving any evidence of its occurrence until a sudden colour change or formation of a precipitate indicates that the reaction has gone to completion. The reaction between  $\text{HIO}_3$  and  $\text{NaHSO}_3$  is a clock reaction whose completion is indicated, in presence of starch solution, by the sudden appearance of the blue-black colour.
19. The saw dust which is produced in considerable amount in a saw mill remains suspended in air in a finely divided state. Because of the very large surface area at which oxygen is in contact with combustible particles, the combustion, if initiated, will take place at a very fast rate and may cause an explosion.
20. (i) A faint pink colour very slowly (over a period of 5-10 minutes) appears on the surface of the particles due to the formation of  $\text{HgI}_2$ .






But as the surface area of contact between the reactants is very small, only a slight reaction takes place.


- (ii) On grinding, the particle size of the reactants is reduced. Fresh surface, therefore, gets exposed and more reaction takes place. The intensity of the colour will thus go on increasing as grinding is continued and finally the whole material will become red.
- (iii) On addition of water, KCl will dissolve but not  $\text{HgI}_2$  which will appear as a red precipitate.
- (iv) On addition of more KI, the red precipitate will slowly disappear because of formation of  $\text{HgI}_4^{2-}$  complex:



21. (i) Atmospheric oxidation of  $\text{I}^-$  to  $\text{I}_2$ :



- (ii) Chlorination of methane:



- (iii) Decomposition of  $\text{NO}_2$  into nitric oxide and atomic oxygen in the photochemical smog formation:




22. According to Law of Mass Action, the rate of a reaction at any given instant depends on the concentration of the reactants at that instant. As the reaction progresses, more and more of the reactants are converted into the products. Thus the concentration of the reactants falls with time and so does the rate of reaction.

23. The speed of a reaction is important as it determines whether the reaction will be of any practical use to us.

24. For determining the concentration of a reactant at a particular instant during the course of a reaction, it is necessary to completely stop the reaction or reduce its velocity to a very low value so that the concentration of the reactant does not change during the course of the titration. Addition of ice-cold water reduces the temperature which causes a marked decrease in the rate of the reaction. The process is known as Freezing (or arresting) the reaction.

25. (1) Decomposition of  $\text{H}_2\text{O}_2$  in aqueous solution:




- (2) Decomposition of ammonium nitrite in aqueous solution:






- (3) Inversion of cane sugar in presence of dilute acid:



- (4) The rate of death of micro-organisms by a disinfectant is approximately proportional to the concentration of live micro-organisms remaining.
- (5) The rate of decomposition of organic matter in the B.O.D. test is approximately proportional to the organic matter remaining.
- (6) Decay of radioactive material.
26. Molecularity of a reaction is defined as the number of molecules involved in the step leading to the chemical reaction. For simple reactions, it is equal to the order of the reaction except when one of the reactants is present in large excess. For example, in the hydrolysis of methylacetate with dilute acid



one molecule of methyl acetate reacts with one molecule of water and so the molecularity of the reaction is 2. However, as discussed on page 23 (Experiment 2.3.2.) and verified experimentally, it is a first order reaction. Such a reaction is known as a Pseudo-Unimolecular reaction.

For a complex reaction occurring in several steps (elementary reactions), each step has its own molecularity depending upon the number of molecules of the reactant or reactants taking part in that step. Molecularity has no significance for the overall reaction.

The order of a complex (multi-step) reaction is given by the order of the rate-determining step, i.e., the slowest step in the sequence of various steps involved in that reaction. The order has to be measured experimentally. Neither the order nor the molecularity of a reaction can be predicted from the stoichiometric equation of the overall reaction.

27. This is done to arrest the reaction at the instant when the concentration of residual alkali is to be determined. On adding the reaction mixture to ice-cold HCl (a known excess), the residual alkali is instantaneously neutralised and the saponification reaction altogether stops. The excess acid does catalyse the hydrolysis of ethylacetate with water to produce acetic acid, but this reaction is extremely slow at low temperature (ice-cold) and does not cause any appreciable error.
28. (a) A reaction between two reactants becomes a first order reaction when one of the reactants is present in large excess. The concentration of this reactant remains practically unchanged and so does not affect the rate of the reaction.



- (b) The rate constant for a second order reaction between two reactants A and B to give products is given by equation (2.37):

$$k = \frac{2.303}{t(a-b)} \log \frac{b(a-x)}{a(b-x)}$$

where  $a$  and  $b$  are the initial concentrations of A & B, respectively. If A is taken in large excess,  $a$  will be much larger than both  $b$  and  $x$ . Then in the above equation,  $(a-b)$  and  $(a-x)$  can be replaced by  $a$ , and we get

$$k = \frac{2.303}{t \cdot a} \log \frac{b \cdot a}{a \cdot (b-x)}$$


or 
$$\frac{2.303}{t} \log \frac{b}{b-x} = ak = k'$$

which is the equation for a first order reaction in respect of B, i.e., in respect of the reactant taken in smaller quantity.


29. (1) Saponification of esters:



- (2) Decomposition of ozone to oxygen:



- (3) Conversion of ammonium cyanate into urea in solution:



30. The rate constant for a third order reaction is given by


$$k = \frac{1}{2a^2t} \cdot \frac{x(2a-x)}{(a-x)^2}$$

where  $a$  is the initial concentration of each of the reactants and  $x$  is the decrease in the concentration of each of the reactants in time  $t$ .

31. For a third or higher order reaction, three or more reacting particles (molecules or ions) must interact (collide) simultaneously. The probability for such a situation to occur is very low. Therefore, third or higher order reactions are extremely rare.

### 32. Third Order Reactions

- (1) Oxidation of nitric oxide to  $\text{NO}_2$ :




- (2) Reduction of  $\text{FeCl}_3$  by  $\text{SnCl}_2$ :





**Fourth Order Reaction:**

Thermal decomposition of potassium chlorate, represented by the equation




is a fourth order reaction.

33. Reactions whose rates do not depend on the concentration of the reactants but remain constant throughout are said to be zero order reactions.

**Examples**

- (i) Photochemical reaction between equimolar mixture of  $\text{H}_2(\text{g})$  and  $\text{Cl}_2(\text{g})$  confined in a tube dipping in water:



- (ii) In the biological waste treatment, the speed of waste utilisation per unit mass of enzyme or bacteria ( $V/E$ ) is found to be independent of waste or substrate concentration ( $s$ ) over fairly large ranges of concentration.
34. It is the time in which the concentration of the reactant/reactants is reduced to one half of its/their initial value.
35. The half-life period of a first order reaction is given by

$$\begin{aligned} t_{1/2} &= \frac{2.303}{k} \log \frac{a}{a-x} = \frac{2.303}{k} \log \frac{a}{a-\frac{a}{2}} \\ &= \frac{2.303}{k} \log 2 = \frac{0.693}{k} \end{aligned}$$

which does not contain any concentration term. Hence the half-life period of a first order reaction is independent of the initial concentration of the reactant. In general, the half-life period (or time required for completion of any definite fraction) of a reaction with equal initial concentration of all the reactants is given by

$$t_{1/2} \propto \frac{1}{a^{(n-1)}}$$

where  $n$  is the order of reaction.

36. A study of chemical kinetics helps in
- (i) Regulating or making a reaction proceed at the desired rate.
  - (ii) Comparing the relative strengths of acids (Experiment 2.3.3).
  - (iii) Understanding the mechanism (description of various elementary steps) of various reactions.



37. The conversion of ammonium cyanate into urea has been







found to be a second order reaction. Evidently, the balanced chemical equation, which shows only one reacting molecule, does not truly represent the conversion.

The reaction has been suggested to proceed via the following steps:




- (i)  $\text{NH}_4\text{CNO} \xrightarrow{\text{fast}} \text{NH}_4\cdot\text{NCO}$   
(Ammonium isocyanate)
- (ii)  $\text{NH}_4\cdot\text{NCO} \xrightarrow{\text{fast}} \text{H-N}=\text{C}=\text{O} + \text{NH}_3$
- (iii)  $\text{H-N}=\text{C}=\text{O} + \text{NH}_3 \xrightarrow{\text{slow}} \text{H}_2\text{N}\cdot\text{CO}\cdot\text{NH}_2$

The last step, being the slowest, determines the rate of reaction. Since it involves two molecules, the order of the reaction is 2.

38. Methyl orange indicator has structure I in neutral medium. In alkaline medium, it exists as II which is orange and in acidic medium, it exists as III (red).






39.





40. Phenolphthalein has structure I in neutral or acid medium and is colourless. In presence of dilute alkali solution, I is converted to II which loses water to give III (resonating ion having red colour). A large excess of a strong alkali converts III into IV which is again colourless.





41.  $\text{Na}_2\text{CO}_3$  is available in market in Analytical Grade form and is quite stable.  $\text{NaOH}$  samples can absorb  $\text{CO}_2$  from atmosphere and so often contain small amounts of  $\text{Na}_2\text{CO}_3$  as impurity.


The neutralisation of  $\text{CO}_2$  with  $\text{NaOH}$  is a two-step process whereas with  $\text{Na}_2\text{CO}_3$  it is a one-step process (reactions 3.10 & 3.11). Therefore, if  $\text{Na}_2\text{CO}_3$  is present as an impurity in  $\text{NaOH}$ , erroneous (higher) results will be obtained.

42. The solution should be heated to boiling to speed up the hydrolysis of metal salts so that the titration can be completed more rapidly.

43. Mineral Acidity arises from

- (i) Hydrolysis of certain salts present in water (reactions 3.4 & 3.5)
- (ii) Contamination with drainage from industrial area

- (iii) Waters receiving drainage from sulphide ore mines contain considerable amounts of  $\text{H}_2\text{SO}_4$  resulting from wet oxidation of the ore:




- (iv) Acid rains in the areas where atmosphere is highly polluted (contains a high percentage of  $\text{SO}_2$ ).

44. Both acidity and alkalinity are expressed in terms of  $\text{CaCO}_3$  whose equivalent weight is 50. 1 ml of N/50 solution, therefore, corresponds to 1 mg acidity or alkalinity and the calculations become simple.

45. If the sample is alkaline to phenolphthalein, it should be neutralised with approximately 0.05 N  $\text{H}_2\text{SO}_4$ . If the sample is acid to methyl orange, a slight excess of pure  $\text{CaCO}_3$  should be added.

46. The pH of the solution should not exceed 7.2 otherwise  $\text{Ag}^+$  will not be precipitated because of complex formation:



47. The excess of the titrant that must be added before the eye can detect the colour change due to the reaction between the titrant and the indicator is called the indicator blank. This must be determined and subtracted from all titrations. To an aliquot of distilled water, equal to the volume of solution at the end-point, is added the same amount of  $\text{K}_2\text{CrO}_4$  indicator as is used in the actual determination, and the volume of  $\text{AgNO}_3$  required to produce a visible amount of  $\text{Ag}_2\text{CrO}_4$  is determined.

To avoid the indicator blank in the chloride ion determination, prepare the indicator solution as follows: Dissolve 5 g of  $\text{K}_2\text{CrO}_4$  in a



little distilled water. Add  $\text{AgNO}_3$  solution until a definite red precipitate is formed. Allow to stand for 12 hours, filter and dilute to 100 ml.

48. The solubility product of  $\text{Ag}_2\text{CrO}_4$  increases with rising temperature and more  $\text{AgNO}_3$  will have to be added to get the end-point. To avoid this, the titration should be performed at room temperature.
49. (i) To remove the colour and to clarify the sample, it is shaken thoroughly with a few drops of alumina cream [ $\text{Al}(\text{OH})_3$  suspended in water, prepared by adding  $\text{NH}_4\text{OH}$  to  $\text{Al}_2(\text{SO}_4)_3$  and washed free of chloride, sulphate and ammonium ions] followed by decantation or filtration.
- (ii) Interference due to  $\text{H}_2\text{S}$  may be removed by adding a crystal of  $\text{ZnSO}_4$ . In case it is not successful, the sample is acidified with  $\text{H}_2\text{SO}_4$ , boiled for a few minutes and neutralised with  $\text{NaHCO}_3$  followed by dilution with distilled water to original volume.
50. Most accurate results are obtained by calculation from complete mineral analysis of the hard water sample (Equation 3.28) but it is a very tedious job and such type of analysis is rarely done. Of all other methods, EDTA method gives the best result, is less cumbersome and less time consuming.
51. Although  $\text{Ca}^{2+}$  (like  $\text{Mg}^{2+}$ ) reacts with Eriochrome black-T indicator to form a wine red complex:



the colour change from wine red to pure blue is not sharp with calcium indicator complex as with magnesium indicator complex. Therefore,  $\text{Mg}^{2+}$  ions have to be added if not present in the hard water.

52. (i) A small amount of the complexometrically neutral magnesium salt of EDTA ( $\text{Na}_2\text{MgY}$ ) is added to the buffer solution.
- (ii) A small amount of  $\text{MgCl}_2$  may be added to the EDTA solution before it is standardised.
53. At higher pH values,  $\text{CaCO}_3$  or  $\text{Mg}(\text{OH})_2$  may get precipitated and the dye (indicator) may change its colour. At lower pH values, the  $\text{Mg}$ -indicator complex becomes unstable and a sharp end-point cannot be obtained. The pH value is adjusted to about 10 by using a buffer solution of  $\text{NH}_4\text{Cl}/\text{NH}_4\text{OH}$ .
54. (a) Using equation 3.28 (p. 48):

$$\begin{aligned} \text{Total hardness} &= 2.5 \times \text{ppm of } \text{Ca}^{2+} + 4.12 \times \text{ppm of } \text{Mg}^{2+} \\ &= 2.5 \times 20 + 4.12 \times 48.6 \\ &= 50 + 200 = 250 \text{ ppm} \end{aligned}$$



Alternatively

Impurity	ppm	epm	Hardness ppm	Alkalinity ppm
$\text{Ca}^{2+}$	20	$20/20 = 1$	$1 \times 50 = 50$	—
$\text{K}^+$	39	$39/39 = 1$	—	—
$\text{Mg}^{2+}$	48.6	$\frac{48.6}{12.15} = 4$	$4 \times 50 = 200$	—
$\text{Na}^+$	23	$23/23 = 1$	—	—
$\text{SO}_4^{2-}$	96	$96/48 = 2$	—	—
$\text{HCO}_3^-$	183	$183/61 = 3$	—	$3 \times 50 = 150$
$\text{Cl}^-$	35.5	$35.5/35.5 = 1$	—	—

Thus, Calcium hardness = 50 ppm

Magnesium hardness = 200 ppm

Total hardness = 250 ppm

As alkalinity is less than total hardness,

$$\begin{aligned}\text{Carbonate hardness (CH)} &= \text{Alkalinity (Equation 3.29)} \\ &= 150 \text{ ppm}\end{aligned}$$

Therefore, Non-carbonate hardness (NCH) = 250-150

$$= 100 \text{ ppm}$$

(b)

Impurity	ppm	epm	Hardness (ppm)	Alkalinity (ppm)
$\text{Mg}^{2+}$	24.3	$\frac{24.3}{12.15} = 2$	$2 \times 50 = 100$	—
$\text{Ca}^{2+}$	40	$40/20 = 2$	$2 \times 50 = 100$	—
$\text{HCO}_3^-$	305	$305/61 = 5$	—	$5 \times 50 = 250$

		200 ppm	250 ppm
Thus, Calcium hardness	= 100 ppm		
Magnesium hardness	= 100 ppm		
Total hardness	= 200 ppm		



As alkalinity is more than total hardness,

$$\begin{aligned}\text{Carbonate hardness (CH)} &= \text{Total hardness (Equation 3.30)} \\ &= 200 \text{ ppm.}\end{aligned}$$

Hence, there is no permanent hardness.

55. Volume of water sample taken = 100 ml

Volume of N/50 HCl used before boiling = 10.0 ml

Volume of N/50 HCl used after boiling = 0.2 ml

$$\begin{aligned}\text{Methyl Orange Alkalinity before} \\ \text{boiling (Experiment 3.1.3, p. 42)} &= \frac{1}{50} \times 10 \times \frac{1}{100} \times 50 \times 1000 \\ &= 100 \text{ ppm}\end{aligned}$$

$$\begin{aligned}\text{Methyl Orange Alkalinity after} \\ \text{boiling} &= \frac{1}{50} \times 0.2 \times \frac{1}{100} \times 50 \times 1000 \\ &= 2 \text{ ppm}\end{aligned}$$

$$\begin{aligned}\text{Therefore, Temporary hardness} \\ \text{of the sample} &= 100 - 2 = 98 \text{ ppm}\end{aligned}$$

56. Volume of water sample taken = 100 ml

10 ml alkali mixture  $\equiv$  8 ml N/10 HCl

Therefore, 20 ml alkali mixture  $\equiv$  16 ml N/10 HCl

Hence volume of alkali mixture added  $\equiv$  16 ml N/10 HCl  
 $\equiv$  16 ml N/10 alkali

Also filtrate  $\equiv$  13 ml N/10 HCl  
 $\equiv$  13 ml N/10 alkali

$$\begin{aligned}\text{Therefore, volume of N/10 alkali} \\ \text{used in precipitating permanent} \\ \text{hardness in 100 ml of the water sample} &= 16 - 13 = 3 \text{ ml}\end{aligned}$$

$$\begin{aligned}\text{Therefore,} \\ \text{Permanent hardness of the sample} &= \frac{1}{10} \times 3 \times \frac{1}{100} \times 50 \times 1000 \\ &= 150 \text{ ppm}\end{aligned}$$

57. Volume of water sample taken = 100 ml

Volume of N/50 NaOH added = 25 ml



Also, filtrate

$$\equiv 21 \text{ ml N/50 HCl}$$

$$\equiv 21 \text{ ml N/50 NaOH}$$

Therefore, volume of N/50 NaOH used  
for precipitating magnesium hardness of

$$100 \text{ ml of water sample} = 25 - 21 = 4 \text{ ml}$$

Therefore, Magnesium hardness  
of the water sample

$$= \frac{1}{50} \times 4 \times \frac{1}{100} \times 50 \times 1000$$

$$= 40 \text{ ppm}$$

58. (i) Lather factor

$$= \text{Volume of soap solution used against} \\ 70 \text{ ml of distilled water}$$

$$= 0.5 \text{ ml}$$

(ii) Strength of soap solution

1000 ml S.H.W.

$$\equiv 0.28 \text{ g CaCO}_3$$

Therefore, 70 ml S.H.W.

$$\equiv \frac{0.28}{1000} \times 70 \text{ g CaCO}_3$$

$$= 19.6 \text{ mg CaCO}_3$$

But volume of soap solution  
used to precipitate hardness  
of 70 ml of S.H.W.

$$= 20.1 - 0.5 = 19.6 \text{ ml}$$

Hence,

19.6 ml soap solution

$$\equiv 19.6 \text{ mg CaCO}_3$$

or

1 ml soap solution

$$\equiv 1 \text{ mg CaCO}_3$$

(iii) Total hardness

70 ml hard water sample

$$\equiv 14.5 - 0.5 = 14 \text{ ml soap solution}$$

$$\equiv 14 \text{ mg CaCO}_3$$

Therefore, Total hardness

$$= 14^\circ \text{Cl} = 14 \times \frac{100}{7} \text{ ppm} = 200 \text{ ppm}$$

$$= 200 \times \frac{1}{10}^\circ \text{F} = 20^\circ \text{F}$$

(iv) Permanent hardness

70 ml boiled water

$$\equiv 5.4 - 0.5 = 4.9 \text{ ml soap solution}$$

$$\equiv 4.9 \text{ mg CaCO}_3$$

$$\text{Therefore, Permanent hardness} = 4.9^\circ \text{Cl} = 4.9 \times \frac{100}{7} \text{ ppm} = 70 \text{ ppm}$$

$$= 70 \times \frac{1}{10}^\circ \text{F} = 7^\circ \text{F}$$




$$\begin{aligned}
 \text{(v) Temporary hardness} &= 14 - 4.9 = 9.1^\circ\text{Cl} \\
 &= 9.1 \times \frac{100}{7} \text{ ppm} = 130 \text{ ppm} \\
 &= 130 \times \frac{1}{100}^\circ\text{F} = 13^\circ\text{F}
 \end{aligned}$$

59. (a)  $\text{NO}_2^-$  oxidises  $\text{I}^-$  to free iodine in acidic medium;




$\text{N}_2\text{O}_2$  is oxidised back to  $\text{NO}_2^-$  by atmospheric oxygen:




Thus, it remains no longer possible to get a permanent end-point as the blue colour keeps on reappearing due to the formation of  $\text{I}_2$  in a cyclic process, and higher results are obtained.

- (b)  $\text{Fe}^{3+}$ , when present in amounts above 10 mg/l, also interferes by oxidising  $\text{I}^-$  to free  $\text{I}_2$  and leads to higher results:



60.  $\text{Fe}^{2+}$ ,  $\text{SO}_3^{2-}$  and  $\text{S}^{2-}$  react with iodine, reducing it to iodide and thus produce lower results,



61. The D.O. in a sample is utilised to oxidise  $\text{Mn}^{2+}$  to  $\text{Mn}^{4+}$  [ $\text{MnO}(\text{OH})_2$  or  $\text{MnO}_2 \cdot \text{H}_2\text{O}$  : reaction 3.52 or 3.52 a] in alkaline medium. This process is known as fixation of oxygen. When acidified,  $\text{MnO}(\text{OH})_2$  gives back an equivalent amount of oxygen,



62. When a 200 ml sample is used for titration, the number of ml of N/40  $\text{Na}_2\text{S}_2\text{O}_3$  used directly gives the D.O. in ppm.

63. At a constant temperature, the mass of a gas dissolved by a given amount of a solvent is proportional to the pressure of the gas in equilibrium with the solution. Henry's law is applicable when

(i) the temperature is not too low,



- (ii) the gas pressure is not very high, and
- (iii) the gas does not dissociate in, or chemically react with the solvent.

64. A, volume of sample before dilution = 10 ml

B, " " after " = 600 ml

D<sub>1</sub>, the D.O. of diluted sample at the start of experiment = 3.9 mg/l (p. 60)

D<sub>2</sub>, the D.O. of the diluted sample after 5 days = 2.1 mg/l

$$\text{B.O.D. of the sample (Eq. 3.63)} = \frac{D_1 - D_2}{A} \times B$$

$$= \frac{3.9 - 2.1}{10} \times 600 = 108 \text{ mg/l}$$

$$= 108 \text{ ppm}$$

65. The B.O.D. test is widely used
- (i) In determining the polluttional strength of domestic and industrial wastes,
  - (ii) In choosing and designing the treatment method for reducing the polluttional strength of such wastes,
  - (iii) In evaluating the purification capacity of natural water courses into which such wastes are to be discharged and
  - (iv) In evaluating the efficacy of various units of the treatment process.
66. Being a first order reaction, complete BOD will be exerted only in infinite time and determination becomes impracticable. The 5-day incubation period is practicable and the BOD<sub>5</sub> values can be used for many considerations as they represent a fairly large percentage (70 to 80%) of the total BOD.


Also, beyond the 5-day period, significant errors may be introduced due to the growth of nitrifying bacteria (which, in raw sewage or primary effluent, are present in insufficient numbers to oxidise any appreciable amounts of reduced nitrogen in the first five days) which consume oxygen in oxidizing reduced nitrogen (reaction. 3.57) which is normally present in sewage.

67. It should be prepared from distilled water by seeding with a small amount of domestic waste water to provide a mixed population of bacteria. A phosphate buffer should be added to maintain the pH at about 7. Phosphate also serves as a nutrient. Salts like FeCl<sub>3</sub> and NH<sub>4</sub>Cl should be added to supply nutrients and small amounts of Na<sup>+</sup>, K<sup>+</sup> and Ca<sup>2+</sup> should be also added to serve as trace elements needed for the growth of bacteria. Finally, it should be saturated with oxygen.



68. (1) Although the dichromate reflux method is preferred because of its superior oxidising ability, applicability to a wide variety of samples, and ease of manipulation (as compared to the use of  $\text{KMnO}_4$ ,  $\text{Ce}(\text{SO}_4)_2$ ,  $\text{KIO}_3$ , etc.), certain compounds like
- (i) straight-chain aliphatic hydrocarbons,
  - (ii) low molecular weight fatty acids,
  - (iii) pyridine, and
  - (iv) aromatic hydrocarbons resist oxidation.
- (2) Chloride ions, usually present in sewage in appreciable amounts, interfere because of their oxidation under the conditions of the experiment.

69. (1) Oxidation of straight-chain aliphatic hydrocarbons and low molecular weight fatty acids is effectively achieved by the use of  $\text{Ag}_2\text{SO}_4$  catalyst. Pyridine and aromatic hydrocarbons are however not oxidised.
- (2) Interference due to chloride ions is removed by complexing with  $\text{HgSO}_4$ :



70. The pH of the reaction mixture should be adjusted between 3 and 4 using acetic acid. At neutral pH, some forms of combined chlorine residuals do not react with KI. However,  $\text{H}_2\text{SO}_4$  should not be used as it increases the interference by  $\text{Fe}^{3+}$  and  $\text{NO}_2^-$ .

71.  $\text{Fe}^{3+}$ ,  $\text{NO}_2^-$ , manganese in valences above 2 and organic sulphides.

72. At low pH, monochloramine also reacts in the first step and interferes in the determination of free chlorine residuals. At high pH, dissolved oxygen gives a colour and interferes.

73. Interference due to  $\text{Cu}^{2+}$  is overcome by complex formation with EDTA. By complex formation with trace metal catalysts, EDTA retards the oxidation of the DPD indicator by dissolved oxygen.

74. Chlorine Demand of a water sample is the amount of chlorine in mg that is reduced to  $\text{Cl}^-$  or converted into other less active forms by the impurities present in 1 litre of the sample.
- Chlorine Demand = Chlorine applied - Residual chlorine.


75. Chlorine-reactable materials likely to be present in water may be divided into the following categories;
- (a) Organics — Hydrocarbons, phenols, amines, humic acids, etc.
  - (b) Inorganics — Ferrous, Manganous ( $\text{Mn}^{2+}$ ), nitrite, sulphide ( $\text{S}^{2-}$  or  $\text{H}_2\text{S}$ ), sulphite, cyanide, ammonia, etc.



- (c) Living organisms — Bacteria, algae, protozoa, etc
76. (i) Organics and cyanide undergo substitution, addition and oxidation reactions with chlorine forming a variety of compounds (some chlorinated waters have been found to contain as many as sixty different chlorinated and other organics).  
 (ii) Inorganic reducing agents like  $\text{Fe}^{2+}$ ,  $\text{Mn}^{2+}$ ,  $\text{S}^{2-}$ ,  $\text{SO}_3^{2-}$  and  $\text{NO}_2^-$  are oxidised to  $\text{Fe}^{3+}$ ,  $\text{MnO}_2$ , elemental S,  $\text{SO}_4^{2-}$  and  $\text{NO}_3^-$  respectively while chlorine is reduced to  $\text{Cl}^-$ .  
 (iii)  $\text{NH}_3$  undergoes a variety of reactions with  $\text{Cl}_2$  giving products like  $\text{NH}_2\text{Cl}$ ,  $\text{NHCl}_2$ ,  $\text{NCl}_3$ ,  $\text{N}_2$ ,  $\text{NO}_2^-$ ,  $\text{NO}_3^-$  etc.  
 (iv) Chlorine destroys living organisms by reacting with enzymes present in their cells.
77. (i) Chlorine dosage — 0.1 to 0.2 mg/l free chlorine residuals.  
 (ii) Contact period — 30 minutes.  
 (iii) pH range — 6 to 7.
78. Free chlorine is readily dissipated in the distribution system and does not afford complete protection against bacteria due to short contact period. In order to prolong bactericidal action, free chlorine residuals are converted into more stable chloramines (reactions 3.70 & 3.71) by adding a little ammonia or ammonium sulphate to chlorinated water. This process is known as stabilising the chlorine.
79. Break-point chlorination is chlorination of a sample to the extent that all the ammonia present in the sample is converted into  $\text{N}_2$  or its higher states (like  $\text{N}_2\text{O}$ ,  $\text{NO}_2^-$ ,  $\text{NO}_2$ ,  $\text{NO}_3^-$ ,  $\text{NCl}_3$ , etc.) and is marked by a minima in the curve obtained by plotting residual chlorine versus applied dosage of chlorine (Figure 14).

#### Explanation

When a small amount of chlorine is applied to a water sample containing reducing materials ( $\text{Fe}^{2+}$ ,  $\text{S}^{2-}$  etc.), it is readily used up and so there is no residual. This stage is shown by part AB of curve II (for impure water). As the amount of chlorine applied is increased, it starts reacting with organics and also with ammonia which produces chloramines (reactions 3.70 & 3.71). Mono— and dichloramines are disinfectants and are determined as combined chlorine residuals. Part BC of the curve thus shows an increase in the amounts of these chloramines. Any further increase in chlorine dosage decomposes the chloramines possibly via the following reactions:









Fig. 14 Break-point chlorination.



The amount of the combined chlorine residuals thus decreases along the curve CD. Point D indicates almost complete decomposition of chloramines. At this stage, known as Break-point Chlorination, there is a marked decrease in the residual chlorine (a minima in the curve). A higher dosage of chlorine appears as free chlorine residuals and total chlorine residuals start increasing. This is shown by the part DE of the curve.

### Significance

A chlorine dosage higher than Break-point chlorination means that the chlorine demand of all the chlorine-reactable materials has been completely met with and free chlorine residuals are available for bactericidal action. It also signifies complete decomposition of  $\text{NH}_3$ , removal of colouring material and modification of taste and odour of the water sample.

80. Treatment with chlorine before filtration of the sample is known as Prechlorination. A higher chlorine dosage is required to satisfy the chlorine demand of filterable matter. This increases the cost but the



quality of water obtained is superior as the chlorinated products with unpleasant tastes and odours may be adsorbed during filtration.

Postchlorination, i.e., chlorination after filtration is cheaper than prechlorination (due to lower chlorine demand) but the treated water may have unpleasant taste and odour.

81. Jackson turbidimetry (also known as Visual turbidimetry) is based on measuring the interference caused to the passage of light through the sample. In this method, the depth (thickness) of the sample required to obscure the image of a standard candle or bulb is measured visually.

Nephelometric turbidity is based on measuring, with a Photoelectric device, the intensity of light scattered by the sample at right angles to the path of the incident light. As the errors of personal judgement are avoided, the results are more reliable.

82. The Coefficient of Fineness of a suspension is the number obtained by dividing the weight of the suspended matter in a sample, in ppm, by the turbidity of the sample. A greater than 1 coefficient indicates a suspension coarser than the standard, while a suspension finer than the standard is characterised by a coefficient less than one.

83. The U.S. Geological Survey have arbitrarily fixed at 100 the turbidity of a water sample containing 100 ppm of  $\text{SiO}_2$ , by weight, in such a state of fineness that a bright platinum wire of 1 mm diameter can just be seen when held at a depth of 100 mm below the surface of the sample, with the eye of the observer being 1.2 m above the wire.

The apparatus consists of a graduated rod, known as turbidity rod, having a 1 mm thick platinum wire inserted into it at right angles near one end, and a wire ring placed, directly above and at a distance of 1.2 m from the platinum wire, near the other end. The rod is lowered vertically into the sample as far as the wire may be seen through the ring. The level of the surface of the sample on the graduated rod gives the turbidity of the sample. The method is used for testing the degree of fineness of the silica standard.

84.  $\text{HgCl}_2$  (Mercuric chloride).
85. In addition to causing aggregation of finely divided particles dispersed in solution, the coagulants help in the removal of
  - (i) True and apparent colour,
  - (ii) Harmful bacteria, algae and other planktons,
  - (iii) Taste and odour-producing substances.
86. Flocculant aids are substances which do not act as coagulants but when present along with a coagulant increase the rate of flocculation.



They are of two types: (a) Naturally occurring materials like Bentonite (a form of clay), (b) Synthetic polymeric materials like Polyacrylamide (which acts very effectively in concentration range 0.1-0.2%).

87. A 50% solution of aluminium sulphate for use as a coagulant is available in the market under the trade name of 'Liquid Alum'.
88. The velocity distribution across the tube (capillary or jet) diameter does not become uniform immediately as an element of liquid enters the tube. A correction factor to minimise the error due to this drawback is known as 'Inlet Correction'. The magnitude of the correction factor decreases with increase in the length of the tube and with decrease in its diameter.
89. Though RW1 and RW2 may be used for determining relative viscosities of oils having an efflux time as low as 30 seconds, for greater accuracy a longer than 200— seconds efflux time is recommended. This reduces the 'Kinetic Energy Correction' which depends on the volume rate flow,  $V/t$ .
90.  $U = 600$  seconds  
 $L = 780$  seconds  
 $H = 420$  seconds

$$\begin{aligned} \text{Viscosity Index of the unknown oil} &= \frac{L - U}{L - H} \times 100 \\ &= \frac{780 - 600}{780 - 420} \times 100 \\ &= \frac{180}{360} \times 100 \\ &= 50 \end{aligned}$$

91. For every degree rise in temperature, there is a decrease of roughly 2% in the coefficient of viscosity of most of the liquids.
92. Lubricants with high Viscosity Index suffer only a small change in viscosity with change in temperature. Such lubricants can therefore be used over widely varying temperatures and are termed as 'all weather lubricants'.
93. (i) Silicones  
 (ii) Polyglycol ethers  
 (iii) Diesters or triesters.
94. Viscosity Index of a lubricating oil is improved by adding hexanol or



linear polymers like polyisobutylenes, poly-methacrylates, poly (alkyl-styrenes), etc. It has been suggested that linear polymers function in the following ways:

- (i) Rise in temperature increases the solubility of the polymer in the oil. The increased concentration of the polymer raises the viscosity of the oil and thus compensates for the decrease in the viscosity of the oil itself.
- (ii) The polymers are in the coiled form; with rise in temperature, the polymer particles tend to uncoil more and this increases the viscosity of the oil.

95. It is that state of a liquid when its viscosity does not change with rise in temperature.

96. Such a lubricant can be prepared by adding appropriate amount of a suitable linear-polymer Viscosity-Index improver.

97. Freezing mixture	For temperature down to
Ice + water	32° F
Ice + common salt	10° F
Ice + $\text{CaCl}_2$	-15° F
Solid $\text{CO}_2$ + acetone	-70° F

98. It is the highest temperature at which an oil does not move when the standard jar containing the oil is kept in a horizontal position for 5 seconds. Pour point is taken to be 5° F higher than this.

99. For oils containing wax, pour point is the temperature at which crystallisation of wax has gone to such an extent that the oil will stop flowing if cooled further. This temperature is known as 'Wax pour point'. For oils free from wax, pour point is the temperature at which the viscosity is so high that the oil will stop flowing, if cooled further, due to further increase in viscosity. This temperature is known as 'Viscosity pour point'.

100. (a) The 'Viscosity pour point' of an oil can be lowered by lowering the viscosity of the oil. This can be done either by removing some of the more viscous constituents of the oil or by adding a component of lower viscosity.

(b) 'Wax pour point' can be lowered either by dewaxing or by adding a suitable pour point depressant.

101. Pour point depressants are materials which, when added to oils containing wax, get adsorbed on the surface of wax crystals during the initial stages of crystal formation. They thus reduce the size of the wax



crystals. They also alter the crystal structure in such a way that the amount of oil held by the crystals by adsorption or by entrainment is reduced. Both these effects enhance the oil flow at lower temperature and thus reduce the 'Wax pour point' of the oil.

102. Paraflow is an important pour point depressant which, when present in concentrations of 1 to 2 per cent, may reduce the 'Wax pour point' of an oil by 50°F or more. Paraflow is a poly-alkyl naphthalene and is prepared by condensing chlorinated wax with naphthalene in the presence of anhydrous aluminium chloride which acts as a catalyst.
103. Air is a bad conductor of heat. It ensures very slow and uniform temperature change whether the oil is being heated or cooled.
104. S.I.T. is the temperature at which ignition occurs (without the introduction of a flame) when an inflammable liquid is allowed to fall in drops into a hot metal crucible.
105. (a) Presence of moisture  
 (b) Vapour pressure of the oil—higher vapour pressure means lower flash and fire points.  
 (c) Whether the test is made by open-cup or closed-cup method—open-cup methods give higher flash and fire points.  
 (d) Any drafts over the testing device in case of open-cup methods will tend to raise the flash and fire points.  
 (e) In case of closed-cup methods, an increase in the ratio of the air space to the surface of the oil exposed increases the flash and fire points. A flash is observed when the atmosphere inside the cup contains about 2% of oil vapour by volume.  
 (f) Rate of heating affects the time available for the vapour to diffuse into air and hence affects the flash and fire points.  
 (g) Frequency of application of test flame  
 (h) Variations in the time of opening the shutter  
 (i) Variations in the size of the test flame  
 (j) Variations in the rate of stirring — temperature distribution is uneven if the stirring is too slow. Too rapid stirring produces splashing.
106. Presence of water may raise or lower the flash point. The steam formed on heating may prevent the vapour from igniting and hence raise the flash point. However, steam-distillation of low molecular weight constituents of the oil will tend to decrease the flash point. Oils containing water may split and sputter on heating and thus make the determination of the flash point extremely difficult.
107. Free water from an oil may be removed by
  - (a) Settlement and decantation



- (b) Centrifugal action
  - (c) Absorption by usual dehydrating agents such as anhydrous  $\text{Na}_2\text{SO}_4$ , anhydrous  $\text{CaCl}_2$ , etc.
  - (d) Filtration through a filter paper containing Plaster of Paris.
  - (e) Oils which do not lose more volatile portions on heating may be dried by passing a gentle current of air through them at  $100^\circ\text{C}$ .
108. 'Freaky' flash is the term used for the production of irregular flashes below the true flash point of an oil. Contamination of an oil with small amounts of volatile organic substances is responsible for this.
109. Fatty oils on heating may undergo thermal decomposition. Evolution of vapours of decomposition products and traces of free fatty acids present in the oils gives rise to freaky flashes. Flash points of fatty oils vary between  $300\text{--}500^\circ\text{F}$ .
110. Flash Point 'Closed' is determined by heating the oil in a closed cup; test-flame is injected into the cup through an opening produced temporarily and ignition of vapour takes place inside the cup. Thus, the vapour is not free to diffuse to the atmosphere. Accurate and reproducible results are obtained.
- Flash Point 'Open' is determined by heating the oil in a cup without cover. The surface of the oil is thus exposed to atmosphere. There is loss of vapour which is enhanced by any drafts over the testing device. The results are not reproducible and are higher, by as much as a few to  $50^\circ\text{F}$ , than those obtained with closed-cup methods. Cleaveland Open-Cup is the common accepted device for measuring flash points above  $175^\circ\text{F}$ .
111. In the Abel's apparatus, the oil cup is surrounded by an air jacket which is heated by a water bath. The temperature rises slowly at a rate of about  $5^\circ\text{F}$  per minute. Very precise results are obtained. The method is however slow and is recommended for oils flashing up to  $120^\circ\text{F}$ . In the Pensky-Marten's method, the air jacket surrounding the oil cup is heated electrically or by a gas burner directly. The rate of heating is higher ( $10 \pm 1^\circ\text{F}/\text{minute}$ ). It is the most suitable and most commonly used method for all oils flashing above  $120^\circ\text{F}$ .
112. Air being a bad conductor of heat, it helps in controlling the cooling rate.
113. High-viscosity oils have less ability to penetrate rubber. So, on a time basis, there is some justification for the belief that the deteriorating action of mineral oil on rubber diminishes with increase in viscosity. However, if sufficient time is allowed, swelling is sure to occur.



114. The aniline point of an oil decreases with the increase in the percentage of its aromatic content. Aniline point is therefore inversely related to the aromatic content of the oil.
115. Paraffin-base type lubricating oils as a class have the highest aniline points. The range of their aniline points depends on the degree of refinement.
116. Aniline-point thermometers are available in the following three different ranges:
- (i)  $-38$  to  $+42^{\circ}\text{C}$
  - (ii)  $25$  to  $105^{\circ}\text{C}$
  - (iii)  $90$  to  $170^{\circ}\text{C}$

117. A diesel fuel with a high aniline point will have low aromatic content. This will give an easy start to the engine and will reduce knocking. The ignition quality of a diesel fuel is also reported in terms of Diesel Index which is related to the aniline point by the following expression:


$$\text{Diesel Index} = \text{Aniline point in } ^{\circ}\text{F} \times \frac{\text{API gravity}}{100}$$

For high-speed diesel fuel, the aniline point should be above  $160^{\circ}\text{F}$ .

118. The oil sometimes may contain materials, other than the free acids, that may be easily but slowly attacked by the alkali. Pink colour appears at the end-point due to the addition of an extra drop of alkali. In a few seconds, this alkali is consumed by the easily reactable materials and the pink colour fades away.
119. The esters in the oil may be hydrolysed by the moisture present and thus higher erroneous results may be obtained
120. Appearance of a green or bluish-green colour indicates that the sample contains basic constituents; the total base value can then be determined by titrating the sample with N/100 alcoholic HCl. At the end-point, the colour changes from green to orange or yellowish-orange.
121. The presence of moisture spoils the Wj's solution by decomposing ICI:



122. Sunlight catalyses the decomposition of ICI into  $\text{I}_2$  and  $\text{Cl}_2$ :





123. To prevent the leakage of  $\text{Cl}_2$  or  $\text{I}_2$  vapours that may be formed by decomposition of  $\text{ICI}$ .
124. (i) Steam Turbine lubricants  
(ii) Gear lubricants  
(iii) Crank Chamber oils.
125. (i) The lubricant should be refined in such a way as to eliminate the polar impurities whether initially present or formed in the early steps of the refining process.  
(ii) Such additives should be used as have minimum emulsifying characteristics.  
(iii) The oil should be stable towards oxidation under the conditions imposed upon it.  
(iv) The lubricant should be protected against extraneous contamination.
126. 'Soluble Oils' are oil-in-water emulsions, stabilised by an emulsifying agent such as sodium salt of a carboxylic or sulphonic acid. The ratio of oil to water in the emulsion is normally of the order of 1:20 to 1:60. Since they contain a large concentration of water, they have a much higher specific heat and latent heat of vaporisation than anhydrous oils. So they are used to good advantage in machine shops during cutting, drilling, grinding, etc., of metals where cooling rather than lubricity is of paramount importance.
- They are usually opaque, having milky appearance, but transparent soluble oils (cutting oils or cutting oil emulsions) have also been made which have the practical advantage that they do not mask the work from the vision of the operator.
127. Excessive foaming (formation of oil-air emulsion) of the lubricating oil is a very serious problem in diesel engines, aircraft engines and automatic transmissions. Substances which suppress foaming are called defoamants or antifoams. Silicones are the most effective antifoams (concentrations of about 10 ppm are used). Other antifoams are potassium oleate and sodium alkyl esters of sulphuric acid.
128. The cone will penetrate to a greater depth and thus the observed penetration number of the sample will be higher.
129. The cone will not fall freely and so the test will show lower penetration number.
130. The penetration number of a grease depends mainly on the structure and interaction of the gelling element, the amount of soap and nonsoap thickener present and to some extent on the viscosity of the lubricating oil present. It is also affected by the handling procedure during manu-



facture of grease, the temperature of filling the containers and the rate of cooling.

131. It is the separation of a liquid lubricant from a lubricating grease for any cause.
132. In a grease, the soap crystallizes in the form of threads (fibres) having lengths of the order of 20 or more times their thickness. Most soap fibres are microscopic in size and the grease appears smooth. However, when the fibre bundles are large enough to be seen with naked eye, the grease acquires a FIBROUS appearance. The fibrous structure is also noticeable when the grease is pulled apart. Greases having this fibrous structure tend to resist being thrown off gears and out of bearings. The most common example of a FIBROUS grease is sodium-base grease. Petrolatum also has fibrous structure.
133. It is a mixture of oils and waxes stabilised by a third component and is obtained from still residues of paraffin base crudes after fractionation. It does not leave an oily stain on paper as wax is the external phase and oil the internal phase. It can be used as a grease.
134. It is the name given to a soap in which the soap crystal or fiber is formed by Co-crystallisation of a normal soap (such as metallic stearate or oleate) with a complexing agent (such as metallic salts of short chain organic acids like acetic acid or lactic acid, or the inorganic salts like carbonates or chlorides).
135. A complexing agent usually increases the Dropping Point of a grease.
136. (i) Weight of coal sample,  $w_1$  = 2.5 g  
 Weight of empty crucible,  $w_2$  = 19.35 g  
 Weight of crucible + sample,  $w_3$  = 21.85 g  
 Weight of crucible + sample, after heating at 105-110° C,  $w_4$  = 21.765 g  
 Loss in weight (Moisture) =  $w_3 - w_4$   
 = 21.85 - 21.765  
 = 0.085 g  
 Therefore, % Moisture =  $\frac{0.085}{2.5} \times 100 = 3.4$   
 And weight of crucible + residue, after ignition (Ash),  $w_5$  = 19.595 g



$$\text{Weight of Ash} = w_5 - w_2 = 19.595 - 19.35$$

$$= 0.245 \text{ g}$$

$$\text{Therefore, \% Ash} = \frac{0.245}{2.5} \times 100 = 9.80$$

$$(ii) \text{ Weight of sample, } w_1 = 2.5 \text{ g}$$

$$\text{Weight of empty crucible, } w_2 = 19.345 \text{ g}$$

$$\text{Weight of crucible + sample, } w_3 = 21.845 \text{ g}$$

$$\text{Weight of crucible + sample, after heating at } 950 \pm 20^\circ \text{C, } w_4 = 20.873 \text{ g}$$

$$\text{Loss in weight, } = w_3 - w_4 = 21.845 - 20.873$$

$$= 0.972 \text{ g}$$

$$\text{Therefore, \% Volatile Matter (V.M.)} = \frac{0.972}{2.5} \times 100 = 38.88$$

Moisture

$$= 38.88 - 3.4 = 35.48$$

$$(iii) \% \text{ Fixed carbon (F.C.)} = 100 - [\% \text{ Moisture} + \% \text{ Volatile Matter} + \% \text{ Ash}]$$

$$= 100 - [3.4 + 35.48 + 9.80]$$

$$= 51.32$$


$$\text{Calorific value (Equation 5.3)} = 82 \times \text{F.C.} + \alpha \times \text{V.M.}$$

(Goutel's formula)

$$= 82 \times 51.32 + 80 \times 35.48$$

$$= 7046.64 \text{ cal/g}$$

137. Presence of HCl prevents precipitation of chromates, carbonates and phosphates which are insoluble in neutral solutions. Also the precipitate formed in presence of HCl is coarse and consists of large crystals which are more readily filterable. But excess of HCl should be avoided as solubility of  $\text{BaSO}_4$  increases due to the formation of bisulphate ion:



However, in presence of excess of  $\text{Ba}^{2+}$ , the solubility of  $\text{BaSO}_4$  in a solution containing HCl up to 0.05N is negligible.

138. During precipitation of an insoluble salt, some substances normally soluble in the mother liquor are carried down. This contamination of the precipitate with salts which are otherwise soluble is known as coprecipitation. Nitrate, if present, has to be decomposed by boiling the solution with a large excess of HCl before precipitation. Coprecipitation of  $\text{BaCl}_2$  may however be reduced by carrying out the precipitation at (i) boiling temperature, (ii) low concentration of  $\text{BaCl}_2$  and sulphate



solutions and (iii) slow mixing of the two solutions with constant stirring.

139. Due to loss of acid during digestion, the concentration of the boiling mixture with respect to ammonia may become too large and at the prevalent high temperature, loss of ammonia due to volatilisation may take place. To avoid this, sufficient sulphuric acid should be added during digestion so that 10-15 g of it remains in the free state at the end of digestion.
140. HgO and Hg have been reported to be the best catalysts but their presence leads to the formation of mercurio-ammonium compounds which are not completely decomposed by NaOH. So after digestion, 25 ml of an 8% sodium thiosulphate solution or a 4% K<sub>2</sub>S solution is added which decomposes the mercurio-ammonium compounds and removes mercury as sulphide.
141. Zinc reacts with alkali to form hydrogen gas whose evolution helps in the regular ebullition (boiling) during distillation:



- 142(a)(i) Weight of coal sample  $= 0.24 \text{ g}$   
 Weight of CO<sub>2</sub> formed  $= 0.792 \text{ g}$   
 Weight of H<sub>2</sub>O formed  $= 0.0216 \text{ g}$
- Therefore, % carbon (C)  $= \frac{12}{44} \times \frac{\text{weight of CO}_2}{\text{weight of sample}} \times 100$   
 (equation 5.9)  $= \frac{12}{44} \times \frac{0.792}{0.24} \times 100 = 90$
- % Hydrogen (H) (equation 5.8)  $= \frac{2}{18} \times \frac{\text{weight of H}_2\text{O}}{\text{weight of sample}} \times 100$   
 $= \frac{2}{18} \times \frac{0.0216}{0.24} \times 100 = 1$
- (ii) Weight of coal  $= 1.4 \text{ g}$   
 Volume of N/10 H<sub>2</sub>SO<sub>4</sub> taken  $= 50.0 \text{ ml}$   
 Volume of N/10 NaOH used to neutralise excess of acid  $= 10.0 \text{ ml}$   
 Therefore, volume of excess N/10 H<sub>2</sub>SO<sub>4</sub>  $= 10.0 \text{ ml}$   
 Volume of N/10 H<sub>2</sub>SO<sub>4</sub> neutralised by ammonia  $= 50 - 10 = 40.0 \text{ ml}$



$$\begin{aligned}\text{Therefore, \% Nitrogen (N)} \\ \text{(equation 5.25)} &= \frac{\text{ml of acid neutralised} \times \text{normality} \times 1.4}{\text{weight of coal}} \\ &= \frac{40 \times \frac{1}{10} \times 1.4}{1.4} = 4\end{aligned}$$

$$\begin{aligned}\text{(iii) Weight of coal} &= 3.2 \text{ g} \\ \text{Weight of BaSO}_4 \text{ formed} &= 0.233 \text{ g}\end{aligned}$$

$$\begin{aligned}\text{Therefore, \% Sulphur (S)} \\ \text{(equation 5.19)} &= \frac{32}{233} \times \frac{\text{weight of BaSO}_4}{\text{weight of coal}} \times 100 \\ &= \frac{32}{233} \times \frac{0.233}{3.2} \times 100 = 1\end{aligned}$$

$$\begin{aligned}\text{Hence \% Oxygen (O)} \\ \text{(equation 5.26)} &= 100 - [\text{C} + \text{H} + \text{N} + \text{S}] \\ &= 100 - [90 + 1 + 4 + 1] \\ &= 4\end{aligned}$$

$$\begin{aligned}\text{Gross calorific value} \\ \text{(equation 5.4)} &= \frac{1}{100} [8080\text{C} + 34460(\text{H} - \frac{0}{8}) + 2240 \text{S}] \\ &= \frac{1}{100} [8080 \times 90 + 34460(1 - \frac{4}{8}) + 2240 \times 1] \\ &= \frac{1}{100} [727200 + 17230 + 2240] \\ &= 7466.70 \text{ cal/g}\end{aligned}$$

$$\begin{aligned}\text{Net calorific value (N.C.V.)} \\ \text{(equation 5.5)} &= \text{G.C.V.} - \frac{9\text{H}}{100} \times 587 \\ &= 7466.70 - \frac{9 \times 1}{100} \times 587 \\ &= 7466.70 - 52.83 \\ &= 7413.87 \text{ cal/g}\end{aligned}$$


- (b) Proximate analysis is essential to assess the suitability of a coal for a particular domestic or industrial purpose whereas ultimate analysis is essential to calculate the heating value of coal.

Proximate analysis is comparatively cheaper and simpler as against ultimate analysis which is very tedious and the cost of equipment needed is very high.




However, the two types of analysis are complimentary and, taken together, provide necessary and sufficient data to decide about the quality of coal

143. Cuprous chloride solution being a reducing agent is oxidised to an appreciable extent and acquires a greenish black colour on standing:



Addition of copper turnings, wire or gauze to the storage bottle reduces the solution back to  $\text{Cu}_2\text{Cl}_2$  and the solution acquires a




straw yellow colour.

144. As it is not practicable to shake the apparatus, the rate of absorption of the flue gas constituents would be quite slow. In order to achieve speedy absorption, the surface area of contact between the gas and the absorbent solution is increased by placing a large number of glass tubes or beads in the pipets containing the absorbent solutions.
145. Water may preferentially dissolve some constituents of the flue gas and thus change its composition. The solubility of gases in water is considerably reduced due to the presence of  $\text{NaCl}$ .
146. They impart a colour (reddish) to the confining liquid so that its level in the water-jacketed burette may be conveniently observed.
147. The oxygen absorbent, i.e., alkaline pyrogallol solution can absorb both  $\text{CO}_2$  and  $\text{O}_2$ . Hence the gas sample should be passed through this solution only after the  $\text{CO}_2$  content has been removed. Also the carbon monoxide absorbent, i.e., acid cuprous chloride can react with both  $\text{O}_2$  and  $\text{CO}$ . So the gas sample should be led to this solution after removing  $\text{O}_2$ .

Thus, in order that only one constituent be removed by each absorbent, it is important that the flue gas should be brought into contact with various reagents in the following specific sequence or order:

- (i)  $\text{CO}_2$  absorbent —  $\text{KOH}$  solution
  - (ii)  $\text{O}_2$  absorbent — Alkaline pyrogallol solution
  - (iii)  $\text{CO}$  absorbent — Acid cuprous chloride solution.
148. Pyrogallol, also known as pyrogalllic acid, is 1,2,3-trihydroxybenzene and its structural formula is





149. Acidic gases in the flue gas sample, if present, react with alkali:



They are therefore absorbed along with  $\text{CO}_2$ . Thus higher results for  $\text{CO}_2$  are obtained.

150. These gases are not absorbed by any of the three absorbents used. Unless special modifications are made in the Orsat apparatus to measure their amounts, they will be reported as  $\text{N}_2$ . Hence the results of  $\text{N}_2$  will be higher.
151. Temperature and pressure of the experiment affect the total volume of the gas but not the percentage composition provided they (T & P) remain constant throughout the experiment. This is because the effect of deviation of some constituents from ideal behaviour within normal temperature and pressure ranges is negligible. However, the rate of absorption may slightly be affected.
152. The water-jacket serves the purpose of a thermostat. It helps in keeping the temperature constant during the experiment.

### 153. Instrumental methods

1. Methods —
  - (a) Mass spectrometry
  - (b) Gas chromatography
  - (c) Low temperature fractional distillation
2. They produce detailed analysis of the sample.
3. Require less effort on the part of the operator and results are obtained quickly.
4. Capital investment is very high
5. The apparatus is complex and demands greater maintenance.

### Orsat Apparatus

1. Analysis by Orsat apparatus is also known as constant pressure volumetric analysis or chemical absorption analysis.
2. Scope is limited to the analysis of  $\text{CO}_2$ ,  $\text{O}_2$ ,  $\text{CO}$  and  $\text{N}_2$  ( $\text{H}_2$  & a few hydrocarbons with specially equipped laboratory Orsat apparatus) yet the information available is quite useful for regulating combustion.
3. The procedure is cumbersome and time consuming.
4. The apparatus is inexpensive.
5. The apparatus is very simple and maintenance cost is




154. A fuel gas is a fuel in the gaseous state. It contains some of the combustible gases like  $H_2$ ,  $CO$ ,  $CH_4$  or other hydrocarbons. Small amounts of non-combustible gases like  $CO_2$ ,  $N_2$  and  $O_2$  may also be present. Calorific value may vary from about  $1000 \text{ k cal/m}^3$  to about  $12000 \text{ k cal/m}^3$ .

Flue gas is the term used for the products of combustion of a fuel, coming out of the exhaust pipe of an automobile or the chimney of a furnace. Its major constituent is  $N_2$  (usually more than 50%).  $CO_2$ ,  $CO$  and  $O_2$  are present in varying amounts depending upon the extent of combustion. Small amounts of  $SO_2$ , unburnt  $H_2$  and/or hydrocarbons may also be present. They have high sensible heat that can be utilised with the help of regenerators. Calorific value is very low and increases with the amount of  $CO$ , e.g., Blast Furnace gas that contains up to 25%  $CO$  has a calorific value of about  $800 \text{ k cal/m}^3$ .

155. Time required to decompose the iron ore with acid decreases sharply with the decrease in the particle size of the ore. Ten minutes of proper grinding in an agate mortar often saves hours of treatment with acid.

156. (1) Any organic matter associated with the ore is oxidised to  $CO_2$  during roasting.

- (2) Roasting also decomposes any pyrites present in the ore and removes sulphur as  $SO_2$ :



- (3) Any arsenic impurity is also removed as oxide:




157. When a large excess of  $SnCl_2$  is added during reduction, a much larger amount of  $HgCl_2$  will have to be added to remove the excess of  $SnCl_2$ . This means wastage of reagents. Also, a very thick or heavy precipitate of  $Hg_2Cl_2$  will be formed which slowly reacts with the oxidising titrant ( $K_2Cr_2O_7$  or  $KMnO_4$ ) and also reduces ferric complex formed during the reaction leading to inaccurate results.

158. In all the three cases, the  $Hg_2Cl_2$ , formed initially, immediately reacts with more  $Sn^{2+}$  ions present



forming grey or black mercury in the finely divided state, which reacts with the oxidising titrant and also slowly reduces  $Fe^{3+}$  in presence of  $Cl^-$  ions:



thus giving inaccurate results.



159. (a) To avoid the atmospheric oxidation of  $\text{Fe}^{2+}$  to  $\text{Fe}^{3+}$  which is quite appreciable in hot solution.  
 (b) To avoid the precipitation of Hg on the addition of  $\text{HgCl}_2$ .
160. It indicates that stannous chloride has not been added in excess which means that reduction of  $\text{Fe}^{3+}$  to  $\text{Fe}^{2+}$  may be incomplete.
161.  $\text{H}_3\text{PO}_4$  complexes the  $\text{Fe}^{3+}$  ions formed during the titration and thus removes the yellow colour due to  $\text{FeCl}_3$ . This makes detection of the end-point easier.
162. *Internal Indicator:* A substance that can be added to the reaction mixture to indicate the equivalence point of the titration.

*Example:* Phenolphthalein in acid-alkali titration.

*External Indicator:* An indicator which is not added to the reaction mixture. Rather, a drop of the reaction mixture is removed and mixed with a drop of the indicator on a glazed tile.

*Example:* KSCN is used as external indicator for testing complete reduction of  $\text{Fe}^{3+}$  to  $\text{Fe}^{2+}$  during the reduction of iron ore solution with Zn and  $\text{H}_2\text{SO}_4$ .


*Self Indicator* When one of the reactants itself acts as indicator and no external substance is required.

*Example:* In the titration of oxalic acid with  $\text{KMnO}_4$ , the titrant itself acts as indicator.


163. The external indicator used is a solution of potassium ferricyanide,  $\text{K}[\text{Fe}(\text{CN})_6]$ .

*Preparation:* A small crystal of  $\text{K}_3[\text{Fe}(\text{CN})_6]$  is washed repeatedly with distilled water to remove the superficial coating of the ferrocyanide. The washed crystal is then dissolved in distilled water to get an approximately 0.1 per cent solution.

164. The indicator solution is taken in the form of drops on a dry glazed tile (A glass rod or a dropper may be used). The dichromate solution is then added in small portions to the iron ore solution and after each addition, a drop of the reaction mixture is removed with a clean glass rod and mixed with one of the drops of the indicator. A deep blue colour appears:








As the addition of dichromate solution is continued, the concentration of  $\text{Fe}^{2+}$  ions decreases, and on testing with a fresh drop of the indicator a bluish-green and then green colour appears. The titration is complete at a stage when a drop of the iron solution on being mixed with a drop of the indicator on the tile shows no trace of green—a slightly brownish tint superimposed on the yellow is observed.

165. (1) To get good drops, the glazed tile should be perfectly dry (A piece of blotting paper may be used for drying).
- (2) After each testing, the glass rod must be washed with distilled water otherwise some indicator solution sticking to the tip of the glass rod will get transferred to the reaction mixture and spoil it.
- (3) Each time the glass rod is dipped into the reaction mixture, some  $\text{Fe}^{2+}$  ions are removed and consequently lower results will be obtained. To reduce this loss, testing should be started near the end-point, i.e., after the first titration, the dichromate solution should be run into the  $\text{Fe}^{2+}$  ion solution, without testing, to within 0.5 ml of the previously determined end-point. Then the dichromate solution should be added dropwise, testing the reaction mixture after each addition.  
This helps in two ways:
  - (a) Number of withdrawals for testing is reduced.
  - (b) Concentration of  $\text{Fe}^{2+}$  ions near the end-point is very small and so loss of iron is not appreciable.
166. (1) Detection of the end-point is quite cumbersome.
- (2) Lower results are obtained because of loss of  $\text{Fe}^{2+}$  during testing.
167. It will immediately react with  $\text{Fe}^{2+}$  ions producing the deep blue colour of ferroferricyanide. The ferrous ions thus combined will not be available for oxidation and also the detection of the end-point will not be possible.
168. The hydrogen bubbles escaping the solution may carry along with them appreciable amounts of iron ions. When the bubbles pass through the narrow tube of the funnel, majority of them break and the loss of iron is reduced.
169. A.R. zinc reacts very slowly with dilute  $\text{H}_2\text{SO}_4$ . Copper sulphate increases the rate of dissolution of Zn and thus the production of hydrogen, by setting up a galvanic cell.
170. When HCl is present, some  $\text{KMnO}_4$  may be consumed in the oxidation



of  $\text{Cl}^-$  ions:



Thus  $\text{KMnO}_4$  titration may give higher results.

171. Many iron ores are very difficult to decompose by  $\text{H}_2\text{SO}_4$ . So the solution has to be prepared in  $\text{HCl}$ . If it is to be titrated with  $\text{KMnO}_4$ , the following methods may be used:

- (a) The iron ore solution is reduced with  $\text{SnCl}_2/\text{HCl}$  (excess  $\text{SnCl}_2$  being removed with  $\text{HgCl}_2$ ). The solution is then titrated with standard  $\text{KMnO}_4$  in presence of Zimmermann-Reinhardt reagent ( $\text{MnSO}_4 \cdot 4\text{H}_2\text{O}$  + water +  $\text{H}_2\text{SO}_4$  +  $\text{H}_3\text{PO}_4$ ) which is also known as preventive solution. Presence of excess of  $\text{Mn}^{2+}$  reduces the oxidising power of  $\text{KMnO}_4$ . Also the reducing power of  $\text{Fe}^{2+}$  is increased by the presence of phosphoric acid which complexes  $\text{Fe}^{3+}$  ions. Thus the possibility of the oxidation of  $\text{Cl}^-$  with  $\text{KMnO}_4$  is reduced.
- (b) The best method is to expel  $\text{HCl}$  by evaporating the iron ore solution with  $\text{H}_2\text{SO}_4$ :



and dissolving the residue in dilute  $\text{H}_2\text{SO}_4$  followed by reduction with zinc and  $\text{H}_2\text{SO}_4$ .

172. Reduction with amalgamated zinc is much more rapid than with zinc and  $\text{H}_2\text{SO}_4$ . As no hydrogen is evolved,



there is no loss of iron.

173. AR granulated zinc is taken in a beaker and covered with a 2% solution of  $\text{HgCl}_2$ . The mixture is stirred with a glass rod for about 10 minutes. The solution is then decanted and the residual zinc amalgam formed is washed repeatedly with distilled water by decantation.

174. 1. Sulphurous acid or  $\text{SO}_2$  ( $\text{Na}_2\text{SO}_3/\text{H}_2\text{SO}_4$ )  
 2.  $\text{H}_2\text{S}$   
 3. Titanous chloride ( $\text{TiCl}_3$ )  
 4.  $\text{Mg}/\text{H}_2\text{SO}_4$


175. Both As (III) and Sb (III) react with  $\text{I}_2$  as per the following reactions:






Thus, if arsenic and antimony are present in the trivalent state, a part of iodine liberated by copper will be used up and the results will be lower. Though the reactions are reversible, the backward reaction, namely, the oxidation of  $\Gamma^-$  by  $\text{As(V)}$  and  $\text{Sb(V)}$  above a pH of 3.2 (maintained by buffer) is not appreciable and so no interference is caused.

176. Even when present in trace amounts,  $\text{NO}_2^-$  and nitrogen oxides cause very marked interference by oxidising  $\Gamma^-$  to  $\text{I}_2$ .



Nitric oxide is readily oxidised by air to  $\text{NO}_2$  which in turn






reacts anew with iodide to form more iodine and NO and the cycle



is then repeated. For this reason, when the solution is titrated with thiosulphate in presence of starch, the blue colour returns again and again and no permanent end-point can be obtained.

177. Both nitrite and nitrogen oxides are eliminated by heating with urea in acid medium.




Nitrous acid (nitrite in acid medium) can also be eliminated by treating the solution with sulphamic acid:



178. Any iron present in the ore or alloy gets oxidised to  $\text{Fe}^{3+}$  during






preparation of the solution.  $\text{Fe}^{3+}$  oxidises  $\Gamma$  to  $\text{I}_2$ :



Thus, results will be high.

179. Ethylenediaminetetra-acetic acid (EDTA) and pyrophosphate form stronger complexes with  $\text{Fe}^{3+}$  than with  $\text{Fe}^{2+}$  and thus avoid interference by  $\text{Fe}^{3+}$ .

180. Atmospheric oxidation of  $\Gamma$  is catalysed by low pH,



$\text{Cu}^+$  ion, nitrite ion, nitrogen oxides and sunlight.

181. (a) At low pH values As(V) and Sb(V) will interfere by oxidising  $\Gamma$ .

(b) The reaction between  $\text{Cu}^{2+}$  and  $\Gamma$  goes to completion only under conditions where  $\text{CuI}$  remains insoluble. If the pH is very low,  $\text{CuI}$  dissolves and the reaction becomes reversible:



and results are inaccurate.

(c) Low pH catalyses atmospheric oxidation of  $\Gamma$ .

182. On adding KI to  $\text{Cu}^{2+}$  solution, a white precipitate of  $\text{CuI}$  is formed but the white colour is not visible because of brown colour of  $\text{I}_3$  produced by the reaction of liberated iodine with excess  $\Gamma$ :




183. A small amount of  $\text{I}_2$  gets adsorbed on the surface of  $\text{CuI}$ . On the addition of thiocyanate, the surface layers of  $\text{CuI}$  are converted into less soluble cuprous thiocyanate:



In the process, the adsorbed iodine gets desorbed (which intensifies the blue colour) and is immediately titrated to the disappearance of the blue colour.



184. Reappearance of the blue colour at the end-point indicates
- the occurrence of one or more of the factors that catalyse atmospheric oxidation of  $\Gamma$  (Ex. 180)
  - reaction between the oxidising agent and  $\Gamma$  is slow and sufficient time has not been allowed.
185. Tap water contains considerable amounts of  $\text{Cl}^-$  ions which interfere with the estimation.
186. (i) It prevents the hydrolysis of  $\text{Fe}^{3+}$  ion  
(ii) It discharges the brown colour of ferric alum indicator.
187. Nitrous acid, if present, will react with thiocyanic acid and produce a red colour which may be mistaken for the end-point.
188. A.R. nitric acid is diluted with an equal volume of distilled water and boiled until it is perfectly colourless. Boiling expels any lower oxides of nitrogen.
189. As a drop of thiocyanate solution is added to  $\text{Ag}^+$  ion solution containing  $\text{Fe}^{3+}$  ion, a reddish-brown cloud is first formed which



quickly disappears on shaking because of its reaction with  $\text{Ag}^+$  ion:



As the concentration of  $\text{Ag}^+$  ions decreases, the above reaction becomes slow, i.e., the reddish-brown colour disappears only slowly when the end-point is approaching.

190. Some  $\text{Ag}^+$  ions get adsorbed on the surface of the flocculent precipitate of  $\text{AgSCN}$  and escape reaction unless vigorously shaken. Thus a premature end-point may be obtained and the results will be low.
191. (i) The stream of  $\text{CO}_2$  drives the  $\text{Cl}_2$  produced to the conical flask containing KI solution.  
(ii) It dilutes  $\text{Cl}_2$  and thus helps in more efficient absorption.  
(iii) It also inhibits the back-suction of KI solution into the distillation flask.
192. The guard tube contains some glass beads moistened with KI solution. Any trace of  $\text{Cl}_2$  or  $\text{I}_2$  vapour that escapes absorption in the conical flask is retained by the KI solution in the guard tube.



193.  $\text{Cl}_2$  gas coming from the distillation flask will raise the temperature of the KI solution which may lead to some loss of iodine.
194. It is used for bleaching the yellow colour due to the presence of  $\text{Fe}_2\text{O}_3$ .  $\text{MnO}_2$  imparts a purplish colour which by combination with yellow colour makes the glass appear colourless.
195. It occurs as a black-coloured rock.
196. Both sodium oxalate and sodium arsenite (prepared from A.R.  $\text{As}_2\text{O}_3$ ) are more convenient because they are stable in air and are primary standards. Ferrous sulphate is not a primary standard and is oxidised by atmospheric oxygen. So the operation has to be carried out in the absence of air. Sodium arsenite, though poisonous, costlier and preparation of its solution being cumbersome, gives more reliable results than sodium oxalate because oxalic acid is decomposed at higher temperatures into  $\text{CO}$  and  $\text{CO}_2$ . The extent of decomposition at a sulphuric acid concentration below 20% is however very small.


197. (a) The half cell reaction for the oxidation of iodide to iodine monochloride is given by



which shows that there is 2-electron change per iodide ion.

$$\begin{aligned}\text{Hence the equivalent weight of KI} &= \frac{\text{Mol. wt. of KI}}{2} \\ &= \frac{166}{2} = 83\end{aligned}$$

- (b) The half cell reaction for iodate is given by



which shows 4-electron change per iodate ion. Hence the equivalent weight of  $\text{KIO}_3 = \frac{\text{Mol. wt.}}{4} = \frac{214}{4} = 53.5$

198. Iodine is only slightly soluble in water but highly soluble in the organic layer which is immiscible with water. A drop of  $\text{KIO}_3$  added from the burette remains in the aqueous layer and the reaction between  $\text{I}_2$  and  $\text{KIO}_3$  will not take place unless they are brought into intimate contact by vigorous shaking.
199. At lower  $\text{HCl}$  concentrations, the rate of reaction near the end-point becomes very slow and may lead to an over-consumption of  $\text{KIO}_3$ .
200. Any chloride and/or extra oxalate ions contaminated with the precipitate




will consume extra  $\text{KMnO}_4$  solution and thus the results will be higher.

201. When magnesium content of limestone is high, magnesium oxalate gets coprecipitated with calcium oxalate. In such a case, redissolve the precipitate of calcium oxalate on the filter paper and in the beaker in 20-25 ml of hot dilute  $\text{HCl}$ . Dilute to about 100 ml and precipitate with about 5 ml of hot 8% ammonium oxalate and proceed as per the normal procedure.
202. The combined filtrate and washings from the oxalate precipitation (calcium estimation) are diluted to a known volume (say, 250 ml). 50 ml of this solution is titrated with a standard solution of EDTA at a pH around 10, using Eriochrome Black-T as indicator (3.3.2, p. 53). The results are reported as Magnesium oxide.
203.  $\text{CaCO}_3$  does not react with iodine and so does not interfere.  $\text{MgO}$  reacts very slowly and so slightly higher results may be obtained.
204. Both calcium oxide and calcium hydroxide are more soluble in sucrose solution than in water.  $\text{CaCO}_3$  is relatively insoluble and is removed by filtration.
205. Glass beads help in grinding of lime and thus facilitate its extraction with sucrose solution.
206. Firstly,  $\text{MgO}$  does not react with water to any great extent, except on long standing. Secondly, solubility of  $\text{Mg}(\text{OH})_2$  is very very low and any small amount formed is retained by the filter paper.
207. (a) Slaking is hydration of quick-lime to give calcium hydroxide (reaction 7.2). When lumps of quick-lime are added to water
  - (i) about 2 parts by weight of quick-lime react with 1 part of water
  - (ii) the lumps disintegrate and crumble to give a fine powder called 'Slaked' or 'Hydrated' lime
  - (iii) about 2.75 Kcal of heat are evolved per kg of lime slaked
  - (iv) the breaking of lumps and conversion of water into steam due to the high heat of reaction produce crackling and hissing sound
  - (v) the volume of slaked lime is about 2 to 3 times the volume of quick-lime used.
- (b) The rate of slaking reaction decreases with
  - (i) increase in the percentage of  $\text{MgO}$
  - (ii) increase in the amount of other impurities
  - (iii) increase in lump size
  - (iv) decrease in porosity



- (v) decrease or increase in the temperature of calcination of lime-stone during manufacture of lime.

208. Quick lime slowly absorbs moisture and  $\text{CO}_2$  from atmosphere:



Its available lime therefore goes on decreasing on continued exposure to air.

209. A suspension of slaked lime in water is termed as milk of lime. Its filtrate, which is the clear aqueous alkaline solution of calcium hydroxide is known as lime water.

210. When lime-stone is calcined at low temperature, the decomposition of  $\text{CaCO}_3$  is incomplete. The product, which is porous and whose volume is not much less than that of the original lime-stone, is known as 'Soft' lime. Because of lower CaO content, soft limes slake slowly.

Calcination of lime-stone at high temperature produces a more compact and dense product which is known as 'Hard' or 'Over-burnt' lime. Some lime reacts with  $\text{SiO}_2$  and  $\text{Al}_2\text{O}_3$  producing silicates and aluminates. Chemical reactivity or rate of slaking reaction is lower because of decreased surface area (due to higher density) and lower CaO content.

211. On the basis of the amount of CaO present and the nature of the associated materials such as MgO,  $\text{SiO}_2$  and  $\text{Al}_2\text{O}_3$ , limes are classified as:

(a) *Fat or High-calcium limes*

- (i) contain about 95% CaO and small amounts of impurities like MgO,  $\text{SiO}_2$ ,  $\text{Al}_2\text{O}_3$ ,  $\text{Fe}_2\text{O}_3$ , etc.,
- (ii) slake rapidly with evolution of large amounts of heat and a large increase in volume,
- (iii) have good sand-carrying capacity and mortar sets to a strong mass.

(b) *Lean or Low-calcium limes*

- (i) contain 70-80% CaO, the remaining being MgO,  $\text{SiO}_2$ ,  $\text{Fe}_2\text{O}_3$  and  $\text{Al}_2\text{O}_3$ ,
- (ii) slake slowly with smaller increase in volume, require less water and evolve less heat,
- (iii) have low sand-carrying capacity and mortar develops lower strength.

(c) *Magnesium limes*

- (i) contain 10-25% MgO; the percentage of impurities like  $\text{SiO}_2$ ,  $\text{Al}_2\text{O}_3$  and  $\text{Fe}_2\text{O}_3$  being small,




- (ii) slake slowly with less evolution of heat and less expansion as compared to fat limes,
  - (iii) have lower sand-carrying capacity; mortar is plastic, can be easily worked, sets slowly to a harder but more smooth surface; so used as finishing coat in lime plastering.
- (d) *Dolomitic or High-magnesium limes*
- (i) contain 25-40% MgO,
  - (ii) slake very slowly with very little expansion and evolution of heat,
  - (iii) are too costly to be used in masonry work; mainly used as flux in metallurgical operations and for production and repair of basic refractories.
- (e) *Hydraulic limes*
- (i) contain 70-90% CaO, 10-30% clayey matter ( $\text{SiO}_2 + \text{Al}_2\text{O}_3 + \text{Fe}_2\text{O}_3$ ) and less than 2% MgO,
  - (ii) slake very slowly with very small expansion and evolution of heat,
  - (iii) set under water without shrinkage (do not crack) and are used as inferior grade natural cements,
  - (iv) are further graded into:
 

Feebly hydraulic	—	10-15% clayey matter
Moderately hydraulic	—	15-20% " "
or Semihydraulic		
Eminently hydraulic	—	20-30% " "

212. There may be some loss of nitrogen on addition of the acid-mixture if the whole of the sample does not come in immediate contact with salicylic acid.
213. Phenol or benzoic acid may be added to fix the nitrate nitrogen in the form of the corresponding nitroderivative but they are less satisfactory than salicylic acid.
214. After the reaction of the sample with acid mixture, anhydrous sodium thisoulphate is added which reacts with  $\text{H}_2\text{SO}_4$  to produce  $\text{SO}_2$ :




The  $\text{SO}_2$  so produced reduces nitrosalicylic acid to aminosalicylic acid:





215. It is the process of raising crops on a soil alternately in such a way that one crop increases concentration of a particular nutrient that is depleted by the other. Thus planting of legume crops (peas, beans, grams, etc.) increases the nitrogen content of soil and so this crop may be alternated with wheat or other crops needing large amounts of nitrogen for their growth.
216. Organic farming includes the use of crop rotation and organic manures such as animal wastes for increasing soil fertility. For organic farming to be feasible, farmers must have plenty of livestock. An organic manure of recent discovery is obtained by drying algae, fungi and mosses and converting them into powder. Large scale organic farming may indirectly help in energy conservation and also reduce environmental pollution.
217. Compost is a cheap organic manure containing appreciable amounts of nitrogen and phosphorus. It is easily prepared by the farmers on the farm by burying waste plants, leaves and animal dung in pits and covering them with soil, where anaerobic decay takes place.
218. With a hope to increase the crop yield, farmers tend to overfertilize their fields. Use of fertilizers more than the optimum amounts
- leads to economic loss
  - may become toxic to certain plants
  - may increase weeds, and
  - may become the cause of environmental pollution—nutrients drained from fields to lakes cause eutrophication (excessive algal growth).
219. Heating the solutions above  $45^{\circ}\text{C}$  may hydrolyse molybdate to molybdic acid:



which will be filtered along with ammonium phosphomolybdate and will consume additional alkali. Hence, the results will be higher.

220. The yellow colour indicates that the precipitate of ammonium phosphomolybdate is in the finely divided state and is not being retained by the filter paper. The precipitate should be made afresh.
221. (a) The filtrate should not decolourise 1 ml of distilled water containing 1 drop of N/10 NaOH and 1 drop of phenolphthalein.
- (b) The colours produced by 5 drops of filtrate and 5 drops of washing liquid (1%  $\text{KNO}_3$ ) with one drop of methyl red should match.
222. Any organic or inorganic material of natural or synthetic origin which is added to the soil to supply elements essential to plant growth and



thereby increase the crop yield is known as a fertilizer.

223. In addition to C, H and O, some or all of the following elements are known to be essential for the proper development of one or more plants.

- (a) *Macro-nutrients* — Nitrogen, phosphorus and potassium are needed in relatively large amounts.
- (b) *Secondary nutrients* — Calcium, Mg and S are needed in relatively smaller amounts.
- (c) *Micro-nutrients* — Fe, B, Mn, Cu, Zn, Co, Se, Mo and Cl are needed only in trace amounts.

224. The N-P-K value of a fertilizer represents the percentage of N,  $P_2O_5$  and  $K_2O$  equivalent to nitrogen, phosphorous and potassium respectively, present in the fertilizer:

Thus, the N-P-K value of urea	= 45-0-0
Diammonium phosphate	= 21-53-0
$K_2SO_4$	= 0-0-34

225. The principal components of the majority of phosphate rocks is Fluorapatite  $[Ca_3(PO_4)_2 \cdot 3CaF_2]$ . Other substances that may be present include small amounts of  $CaCO_3$ ,  $CaCl_2$ ,  $CaSO_4$ ,  $MgCO_3$ , silica,  $Fe_2O_3$ ,  $Al_2O_3$ , combined water and organic matter.

226. B.P.L. stands for Bone Phosphate of Lime and is the trade name for the  $Ca_3(PO_4)_2$  content of phosphate rock. A rock with high B.P.L. content fetches higher price.

227. Phosphorous in soils and in fertilisers is generally present as orthophosphates — water soluble ammonium phosphate and monocalcium phosphate  $[Ca(H_2PO_4)_2]$ , less soluble basic calcium phosphate  $[Ca_3(PO_4)_2]$  — though other forms of phosphate and organophosphorus compounds are also encountered. Available or assimilable phosphorus includes only that part of total phosphorus which the plants can absorb from the soil. There is no general agreement on the best chemical method of measuring phosphorus availability and the various procedures proposed for available soil-phosphorus are:

- (a) Extraction with water followed by extraction with neutral ammonium citrate solution
- (b) Extraction with dilute acid
- (c) Extraction with fluoride
- (d) Extraction with bicarbonate.




228. A known weight of the powdered sample is first extracted with several successive small portions of distilled water. The residue is then extracted with a neutral solution of ammonium citrate under prescribed conditions. The residue is then decomposed with aqua regia and the phosphorus content determined and reported as citrate-insoluble phosphorus. The difference between the total phosphorus and citrate-insoluble phosphorus is a measure of the available phosphorus.



229. Nitrogen —  $\text{NH}_4^+$ ,  $\text{NO}_3^-$

Phosphorus —  $\text{H}_2\text{PO}_4^-$

Potassium —  $\text{K}^+$





231. When moist bleaching powder is allowed to stand, some chlorite ( $\text{ClO}_2^-$ ) is formed which reacts very slowly with iodide in presence of acetic acid:



This slow liberation of iodine causes the colour to reappear at the end-point. In presence of sulphuric acid, however, the above reaction is complete in 2-3 minutes and a stable end-point can be obtained. Since chlorite is also a bleaching agent, it need not be differentiated from hypochlorite.

232. When strongly acidified with HCl, calcium chlorate, which is usually present in small amounts and is not a bleaching agent, also reacts slowly with iodide liberating additional iodine and



thus higher results are obtained.

233. The arsenite method is considered to be more accurate than the iodometric method as there is no risk of the interference from chlorate,



To 50 ml of the sample solution in a conical flask, add a known excess of 0.1 N  $\text{As}_2\text{O}_3$  solution. Mix well by shaking and titrate the excess  $\text{As}_2\text{O}_3$  with 0.1 N iodine solution, after adding 2 ml of freshly prepared starch solution. Calculate available chlorine from the amount of  $\text{As}_2\text{O}_3$  consumed.

234. Bleach liquor is the trade name for a clear 'Hypochlorite solution' generally used for bleaching purposes. It is made by shaking bleaching powder with distilled water, allowing the 'mud' to settle down and decanting off the clear supernatant liquid. It generally contains from 20 to 35% available chlorine. A relatively weaker (10-15% available chlorine) but more stable bleach liquor is prepared by passing  $\text{Cl}_2$  gas into a cold solution of  $\text{NaOH}$ .
235. The cloth is dipped into the bleach liquor and then drawn through vats containing dilute  $\text{HCl}$  or  $\text{H}_2\text{SO}_4$ . To remove excess of chlorine from cloth, it is drawn through an antichlor bath containing  $\text{Na}_2\text{S}_2\text{O}_3$  or  $\text{NaHSO}_3$  solution. Finally, it is freely washed with water, squeezed, dried and calendered.
236.
  1. It should contain at least 35% available chlorine.
  2. A 6% suspension of it in distilled water, thoroughly stirred for 15-20 minutes, should settle clear within one hour so that bleach liquor may be prepared without much loss of  $\text{Cl}_2$ .
237. The strength of a bleaching powder sample in French or Gay-Lussac Degrees indicates the number of litres of  $\text{Cl}_2$  gas, measured at  $0^\circ\text{C}$  and 760 mm pressure, that can be obtained from one kg of the sample (100 French Degrees = 31.78%  $\text{Cl}_2$ ).
238.
  - (1) Hydrogen peroxide
  - (2) Ozone
  - (3) Chlorine gas
  - (4) Benzoyl peroxide ( $\text{C}_6\text{H}_5\text{COO}$ )<sub>2</sub>
  - (5) Nitrosyl chloride ( $\text{NOCl}$ ).
239. The lower end of the capillary tube is flattened, ground and polished carefully to get a large dropping surface with a sharp boundary.
240. The capillary slows down the flow of the liquid through the tip. The final adjustment of the rate of fall of the drops however is made by regulating the screw-pinch-cock on the rubber tubing.
241. The passage of the liquid meniscus may not exactly coincide with the marks X and Y when the drop falls. The consequent error can be eliminated with the help of graduation. The number of divisions through



which the liquid meniscus passes for the formation of one drop is determined. Let it be 5. Also, let the first drop formation commence at the 4th division below mark X and the last drop fall when the liquid meniscus is 2 divisions below the mark Y. Then the correction factor for the number of drops is  $(+ 4 - 2) \cdot \frac{1}{5} = + \frac{2}{5}$  drops, that is  $2/5 (= 0.4)$  should be added to the number of drops counted to get the true number of drops formed from a volume of liquid between marks X and Y.

242. The glass tube serves as an air-vent so that the pressure in the receiving bottle remains the same as the atmospheric pressure.
243. Rise in temperature of a liquid increases the kinetic energy of its molecules. This decreases intermolecular forces of attraction, resulting in a decrease in surface tension. At the critical temperature of a liquid, its surface tension vanishes altogether since, at this temperature, the surface of separation between the liquid and its vapour disappears completely.
244. It is the force of tension that always exists along the surface of separation between any two phases of different nature, e.g., the interface between immiscible liquids, between solids and gases, and between solids and non-dissolving liquids. Surface tension is only a specific case of interfacial tension when a liquid is in contact with air saturated with the liquid vapour.
245. The unbalanced forces of attraction acting along the surface of each liquid (individual surface tensions) are partly compensated by the forces of attraction that the molecules of one liquid have for the molecules of the other.
246. Parachor is equal to the molecular volume of a liquid at a temperature at which its surface tension is unity. It is both an additive as well as a constitutive property.
247. All such substances which when added to a solvent (particularly water) decrease its surface tension are called surface active agents or surfactants. Examples— soap and alcohol decrease the surface tension of water.
248. As a liquid tends to have minimum surface area, any attempt to increase the surface area will require some work to be done. The amount of work required to increase the surface area of a liquid by  $1 \text{ cm}^2$  is known as the surface energy of the liquid. It is expressed in  $\text{ergs/cm}^2$ . Surface energy is numerically and dimensionally equal to surface tension ( $\text{dynes/cm}$ ).



## Bibliography

- Chemistry of Engineering Materials. Fourth Edition, Robert B. Leighou, International Chemical Series; McGraw-Hill Book Co. Inc., New York, 1953.
- Applied Chemistry for Engineers, Third Edition, Eric S. Gynge; Edward Arnold (Publishers) Ltd., London, 1960.
- Chemistry in Engineering and Technology, J.C. Kuriacose and J. Rajaram; Tata McGraw-Hill Publishing Company Ltd., New Delhi, 1984.
- Chemistry in Industry, S.K. Chatterjee; Book Syndicate Private Ltd., Calcutta, 1987.
- Chemistry—An Experimental Science, Chemical Education Material Study; W.H. Freeman and Company, Cooperating Publishers, San Francisco, 1963.
- Chemistry for Environmental Engineering, Third Edition, Clair N. Sawyer and Perry L. McCarty; McGraw-Hill Book Company, New York, 1978.
- Environmental Pollution, Second Edition, Laurent Hodges; Holt, Rinehart & Winston, U.S.A., 1977.
- Experiments in Inorganic Chemistry, Third Edition, Department of Chemistry, South Dakota College, Brookings; Burgess Publishing House, Minnesota, 1965.
- A Text-Book of Quantitative Inorganic Analysis, Third Edition, Arthur I. Vogel; The English Language Book Society and Longmans Green & Co. Ltd., London, 1962.
- A Systematic Handbook of Volumetric Analysis, Francis Sutton; Butterworths Scientific Publications, London, 1955.
- Technical Methods of Analysis, R.C. Griffin, McGraw-Hill Book Company, Inc., New York, 1955.
- Standard Methods of Chemical Analysis, Sixth Edition, Frank J. Welcher (Ed); D. Van Nostrand Company, Inc., Princeton, New Jersey, 1963.
- Standard Methods for the Examination of Water and Wastewater, 16th Edition, APHA-AWWA-WPCF, Washington, 1985.
- Water Quality and Treatment, Third Edition, The American Water Works Association, Inc., McGraw Hill Book Company, New York, 1971.
- Manual of Public Health Engineers, Vol I, V.S. Sharma; International Book Traders, Delhi, 1985.
- Standard Handbook of Lubrication Engineering, American Society of Lubrication Engineers, McGraw-Hill Book Company, New York, 1968.
- The Lubrication Engineers Manual, First Edition, Charles A. Bailey & Joseph S. Aarons (Eds); United States Steel, 1981.
- The Performance of Lubricating Oils, Second Edition, H.H. Zuidema; Reinhold Publishing Corporation, New York, 1959.
- Lubricating and Allied Oils, Fourth Edition, E.A. Evans; Chapman & Hall Ltd., London, 1963.
- Theory & Practice of Lubrication Systems, Alexandru Nica & P.A.J. Scott; Scientific Publications (Great Britain) Limited, London, 1969.
- Effective Lubrication, Allen F. Brewer; Robert Krieger Publishing Co., Huntington, New York, 1974.



Handbook of Greases, Lubricants and Refining of Petro Chemicals, First Edition, R.K. Malik and K.C. Dhingra; Small Industries Research Institute, Delhi, 1975-76.  
Fuels—Solid, Liquid & Gaseous, Fifth Edition, J.S.S. Brame and J.G. King; Edward Arnold (Publishers) Ltd., London, 1961.



# SUBJECT INDEX

Abel's Flash point apparatus 95-6, 212

Absolute viscosity 87

Acid value 100

Acidity 35-6, 38

Activation energy 16, 28

Alkali number 35-6, 39-43

All weather lubricants 209

Alumina cream 199

Amalgamated zinc 224

Analysis of flue gases 134-7

Aniline point 97-9, 213

Antifoams 214

Arrhenius equation 28

Ash content 120-22, 216

Available carbon dioxide 161

Available chlorine 177, 235

Available lime 166-9, 230

Available oxygen 152-60

Available phosphorus 233

Base number (value) 100

Biocarbonate alkalinity 40

Bioclimical oxygen demand 60, 204

Blast Furnace gas 229

Bleach liquor 235

Bleaching powder 70, 176, 234

Bleeding of greases 215

BOD 60

Bottle standards 73

Boundary lubrication 84

BPL 233

Brass 146

Break point chlorination 66, 206-7

Calcium hardness 52-5

Calcium in limestone 162-4

Calcium carbonate minerals 160

Calcon indicator 2, 52

Calorific value 216, 218

Carbon content of coal 125-6, 217

Carbon dioxide in flue gas 134-6

Carbon dioxide in water 36-7

Carbon monoxide in flue gas 134-6

Carbonate alkalinity 40-2

Carbonate hardness (CH) 48

Caustic value 166-7

Chalk 160

Chemical equilibrium & chemical kinetics 10

Chemical Oxygen Demand 62-4

Chloramines 65-6

Chloride content 43-4

Chloride of lime 176

Chlorination 65

Chlorine Demand 69, 205

Chlorine dosage 69, 206-7

Chlorine reactable materials 205-6

Chlorine residuals 66-9, 205-7

Citrate-insoluble phosphorus 234

Clinker 121

Clock reaction 21, 191

Cloud point 91-4

Coagulants 208

Coagulation 74-6

Coal 118

COD 62

Coefficient of fineness 208

Coefficient of friction 85

Coefficient of viscosity 88, 209

Coke 119

Collision theory 15

Combined chlorine residuals 67-8

Combined oxides 162

Combustible liquids 95

Combustion 133

Compost 232

Confining liquid 134, 219

Consistency 112

Contact period 69-70

Copper in solution of ore or brass 146

Copper ores 145

Coprecipitation 216-7

Critical temperature 236

Crop rotation 232

Cutting oils 214

Defoamants 214

Demulsibility 109-11

Determination of

acid value of oil 101

acidity of water 38

alkalinity 39

aniline point 98

ash content 121



- available chlorine 177
- available lime 166, 168
- available oxygen in pyrolusite 153
- calcium hardness 52
- calcium in limestone 162
- chloride content 44
- chloride demand 69
- chloride residuals 65, 67
- cloud point 92
- COD 62
- copper 146
- CO<sub>2</sub> in flue gas 134
- CO<sub>2</sub> in water 36
- CO in flue gas 134
- dissolved oxygen 56
- dissolved solids 80
- dropping point 115
- energy of activation 27
- fixed solids 81
- flash point 95
- inorganic acidity 102
- iodine value 107
- iron by KMnO<sub>4</sub> 143
- iron by K<sub>2</sub>Cr<sub>2</sub>O<sub>7</sub> 139
- magnesium hardness 52
- oxygen in flue gas 134
- nitrogen in coal 130
- nitrogen in fertilizer 170
- nitrogen in flue gas 134
- penetration number 113
- permanent hardness 51-2
- phosphate content 173
- pour point 92
- rate constant of a first order reaction 23
- rate constant of a second order reaction 29
- saponification value 104
- settleable solids 81
- silver 150
- steam emulsion number 111
- strong acid number 102
- sulphur 127
- surface tension 181
- suspended solids 79
- temperature coefficient 27
- temporary hardness 51-2
- total solids 78
- turbidity 73
- viscosity 87
- volatile matter 123
- volatile solids 81
- Dichloramine 65, 68, 206
- Diesel index 213
- Dilution water 62, 204
- Disinfection 65, 69-70, 177
- Dissolved carbon dioxide 36-7
- Dissolved oxygen (DO) 56
- Dissolved solids 77, 80
- Dolomitic limes 231
- Drop number method 181-3
- Dropping point 115-7, 215
- Dynamic viscosity 87
- EDTA 50
- Efflux time 91, 209
- Emulsions 108-9
- Energy of activation 28
- Equilibrium 187
- Equilibrium constant 11-3, 187
- Eriochrome black T 2, 50
- Essential elements 169, 233
- Explosive range 94
- External indicator 222-23
- Extreme pressure additives 84
- Factors affecting the rate of a reaction 15-7
- Fatty oils 84-5, 105, 215
- Ferrous in iron ore 139-40
- Fertilizer 232-3
- Fibrous grease 215
- Fire point 94
- Fire triangle 94
- First order reaction 22
- Fixation of oxygen 58, 203
- Fixed carbon 124, 216
- Fixed solids 78-81
- Flammable liquids 94-5
- Flash point 94-7, 211
- Flocculant aids 208-9
- Flocculation 74
- Flue gas 133-7, 221
- Fluid film lubrication 84
- Fourth order reaction 195
- Freaky flash 212
- Free chlorine residuals 66-8
- Freezing mixtures 210
- Friction 83
- Gas locks 95
- Gay-Lussac degree 235
- Gelling agents 112
- Goutel's formula 124
- Greases 112-7
- Gross calorific value 125, 218
- Haber process 188
- Half life period 195
- Hard lime 230
- Hardness 46
- Hehner's method 48
- Henry's law 203
- Higher calorific value 125, 218



- Horrock's test 69  
 Hydrodynamic lubrication 84  
 Hydrogen in coal 125-6, 217  
 Hydraulic limes 231  
 Hydroxide alkalinity 40-42  
  
 Ignition source 94  
 Imhoff cone 81  
 Indicator blank 198  
 Indicators 2  
 Industrial cleaners 94  
 Inherent moisture 119-20  
 Inlet correction 88, 209  
 Inorganic acidity 100, 102  
 Interfacial tension 236  
 Internal indicator 222  
 Invert emulsions 109  
 Inversion of cane sugar 193  
 Iodine solution 4  
 Iodine value 105-8  
 iron ores 138  
 Irreversible reactions 190-91  
  
 Jackson's turbidimetry 72-3, 208  
 Jar test 75  
  
 Kjeldahl's method 130  
 Kinematic viscosity 88  
 Kinetic energy correction 88, 209  
 Koettsdoerfer number 103  
  
 Lather factor 49  
 Law of chemical equilibrium 11  
 Law of mass action 15  
 lean lime 230  
 Le Chatelier's principle 11, 14, 188-89  
 Lime 166  
 Limes 230-31  
 Limestone 160, 162, 230  
 Lime water 230  
 Lower calorific value 125, 218  
 Lubricating oils, Greases & Emulsions 83  
  
 Macro-nutrients 169-70, 233  
 Magnesium hardness 49, 52-5  
 Magnesium limes 230  
 Marble 160  
 Methyl Orange Acidity 38  
 Methyl orange Alkalinity 41  
 Methyl Orange Indicator 2, 196  
 Methyl Red Indicator 2, 196  
 Micro-nutrients 233  
 Milk of lime 230  
 Mineral acidity 198  
 Mixed aniline point 98  
 Moisture content 119-20, 215  
 Molecularity of a reaction 193  
  
 Nephelometric turbidity 73, 208  
 Net calorific value 125, 218  
 Neutralisation number 100  
 Nitrogen in coal 129, 217-8  
 Nitrogen in fertilizer 176  
 Nitrogen in flue gas 136  
 Non-carbonate hardness (NCH) 48  
 Non-drying oils 106  
 NPK value 233  
  
 Order of a reaction 22  
 Ores & Alloys 138  
 Organic acidity 100  
 Organic farming 232  
 Orsat apparatus 135, 220  
 Overfertilisation 232  
 Oxygen demand 56  
 Oxygen in coal 132  
 Oxygen in flue gas 136  
  
 Parachor 236  
 Paraffin 211  
 Penetration number 112-3, 214  
 Penetrometer 116  
 Pensky-Marten's flash point 212  
 Permanent hardness 52  
 Petrolatum 215  
 Phenolphthalein acidity 39  
 Phenolphthalein alkalinity 40  
 Phenolphthalein indicator 2, 197  
 Phosphate content 173  
 Phosphate rock 173, 233  
 Plant nutrients 169  
 Poiseuille's equation 87  
 Post chlorination 73, 208  
 Pour point 91-4  
 Pour point depressants 210-11  
 Pre-chlorination 207  
 Primary standards 185  
 Proximate analysis 118, 219  
 Pseudomolecular reactions 193  
 Pysolusite 152-160, 229  
  
 Quick lime 229-30  
  
 Rate constant 22  
 Rate of a reaction 11, 15  
 Redwood viscometer 87-90, 209  
 Relative viscosity 88  
 Residual chlorine 65  
 Reversible reactions 10  
  
 Saponification 30, 194  
 Saponification value 103  
 Second order reaction 22, 29, 194, 196  
 Secondary nutrients 233



- Self indicator 222  
 Semidrying oils 107  
 Settleable solids 78, 81  
 Significance of  
   acid value 100  
   acidity 38  
   alkalinity 39  
   aniline point 97  
   ash content 120  
   chemical oxygen demand (COD) 63  
   chloride content 44  
   cloud & pour points 92  
   CO<sub>2</sub> in water 36  
   Coagulation 75  
   dissolved oxygen (DO) 56  
   dropping point 115  
   hardness 49  
   iodine value 106  
   penetration test 113  
   saponification value 103  
   sulphur in coal 126  
   turbidity 72  
   viscosity & viscosity index 85  
   volatile matter 123  
 Silver ores & alloys 150  
 Slaking of lime 229-30  
 Soap titration 49  
 Soft lime 230  
 Soild point 93, 210  
 Solids 77  
 Soluble oils 214  
 Spalling 122  
 Sparking 125  
 Specific reaction rate 22  
 Spontaneous ignition temperature (SIT) 211  
 Stalagmometer 181-2  
 Standard hard water 3  
 Steady state 187  
 Steam emulsion number (SEN) 110-11  
 Strong acid number 100, 102  
 Sulphur in coal 126, 218  
 Surface area 15, 17, 20, 191  
 Surface energy 236  
 Surface tension 179  
 Surfactants 236  
 Suspended solids 77, 79  
 Temperature coefficient 27  
 Temporary hardness 47, 52  
 Third order reactions 194  
 Threshold energy 16  
 Titration solvents 8  
 Total acidity 38, 100-102  
 Total alkalinity 40  
 Total chlorine residuals 66  
 Total dissolved solids 81  
 Total hardness 52, 54  
 Total iron 139-45  
 Total moisture 120  
 Total nitrogen 170  
 Total solids 77-8  
 Turbidity 72, 208  
 Ultimate analysis 125, 218-9  
 Unworked grease 113  
 Velocity constant 22  
 Viscosity 86-90  
 Viscosity index 86-7, 209  
 Viscosity index improvers 209-10  
 Viscosity pour point 210  
 Viscosity temperature curves 87  
 Viscous-static 210  
 Volatile matter 122  
 Volatile solids 78-81  
 Volhard method 150  
 Water 34  
 Water emulsion test 110  
 Wax pour point 210  
 Wet steaming 180  
 Wij's solution 8, 107, 213  
 Winkler's method 57  
 Worked grease 113  
 Yield value 112  
 Zero order reaction 195  
 Zimmermann-Reinhardt reagent 224





## **APPLIED CHEMISTRY Theory & Practice**

is an amalgam of Theory and Experiments. It serves as a Laboratory Manual on Examination, testing, characterisation and evaluation of a few materials of wide Industrial and Engineering application. The significance and practical utility of the various tests and the inferences drawn therefrom have been described in detail. The derivation of the formulas, where-ever used, the introduction, theory and related discussions are quite elaborate and touch the level of a Theory text.

The book has been designed to cover the Laboratory Courses in Applied Chemistry at the various Engineering and Technical Institutions. The book will be useful to the students where Applied Chemistry is taught at the M.Sc. level and to Public Health/Water Analysis Laboratories. It will also be useful to the students of Industrial Chemistry — a subject that is being introduced at the undergraduate level in some of the Universities.

Students of all levels of intelligence — from very weak to extremely brilliant — will find something of interest to them in the chapter on solutions to viva-voce questions — a Striking feature of the book.

O.P. VERMANI is Assistant Professor of Chemistry at Regional Engineering College, Kurukshetra. He has more than twenty years experience of teaching Applied Chemistry to Engineering students. He is a Gold Medalist of Kurukshetra University for B.Sc. (Hons.) Chemistry. He received his doctor's degree in Analytical Chemistry from the same University in 1980.

A.K. NARULA is a Lecturer in Chemistry at Kurukshetra University, Kurukshetra. He has taught Applied Chemistry to undergraduate students in Regional Engineering College, Kurukshetra. He has obtained his Ph. D. degree from Delhi University, Delhi in 1983 and worked as Post-doctoral fellow in Nice (France). Dr. Narula has to his credit several research papers in Journals of National and International repute.

**ISBN 81-224-0170-8**

**Rs. 65.00**

**WILEY EASTERN LIMITED**

New Delhi Bangalore Bombay Calcutta Madras Hyderabad Pune